# XPLDevices

Generated by Doxygen 1.9.6

1	Hierarchical Index	1
	1.1 Class Hierarchy	1
2	Class Index	3
	2.1 Class List	3
3	File Index	5
•	3.1 File List	5
4	Class Documentation	7
•	4.1 AnalogIn Class Reference	7
	4.1.1 Detailed Description	7
	4.1.2 Constructor & Destructor Documentation	7
	4.1.2.1 AnalogIn() [1/2]	7
	4.1.2.2 AnalogIn() [2/2]	8
	4.1.3 Member Function Documentation	8
	4.1.3.1 calibrate()	8
	4.1.3.2 handle()	8
	4.1.3.3 raw()	9
	4.1.3.4 value()	9
	4.2 Button Class Reference	9
	4.2.1 Detailed Description	10
	4.2.2 Member Enumeration Documentation	11
	4.2.2.1 anonymous enum	11
	4.2.3 Constructor & Destructor Documentation	11
	<b>4.2.3.1 Button()</b> [1/2]	11
	<b>4.2.3.2 Button()</b> [2/2]	11
	4.2.4 Member Function Documentation	12
	4.2.4.1 engaged()	12
	4.2.4.2 getCommand()	12
	<b>4.2.4.3</b> handle() [1/2]	12
	<b>4.2.4.4 handle()</b> [2/2]	12
	<b>4.2.4.5</b> handleXP() [1/2]	13
	<b>4.2.4.6 handleXP()</b> [2/2]	13
	4.2.4.7 pressed()	13
	4.2.4.8 processCommand()	14
	4.2.4.9 released()	14
	<b>4.2.4.10 setCommand()</b> [1/2]	14
	<b>4.2.4.11 setCommand()</b> [2/2]	14
	4.2.5 Member Data Documentation	15
	4.2.5.1 _cmdPush	15
	4.2.5.2 _mux	15
	4.2.5.3 _pin	15

4.2.5.4 _state	15
4.2.5.5 _transition	15
4.3 DigitalIn_ Class Reference	16
4.3.1 Detailed Description	16
4.3.2 Constructor & Destructor Documentation	16
4.3.2.1 DigitalIn_()	16
4.3.3 Member Function Documentation	16
4.3.3.1 addMux()	16
4.3.3.2 getBit()	17
4.3.3.3 handle()	17
4.3.3.4 setMux()	17
4.4 Encoder Class Reference	18
4.4.1 Detailed Description	19
4.4.2 Constructor & Destructor Documentation	19
<b>4.4.2.1 Encoder()</b> [1/2]	19
<b>4.4.2.2 Encoder()</b> [2/2]	19
4.4.3 Member Function Documentation	20
4.4.3.1 down()	20
4.4.3.2 engaged()	20
4.4.3.3 getCommand()	20
4.4.3.4 handle()	21
4.4.3.5 handleXP()	21
4.4.3.6 pos()	21
4.4.3.7 pressed()	21
4.4.3.8 processCommand()	22
4.4.3.9 released()	22
<b>4.4.3.10 setCommand()</b> [1/4]	22
<b>4.4.3.11 setCommand()</b> [2/4]	22
<b>4.4.3.12 setCommand()</b> [3/4]	23
<b>4.4.3.13 setCommand()</b> [4/4]	23
4.4.3.14 up()	23
4.5 LedShift Class Reference	24
4.5.1 Detailed Description	24
4.5.2 Constructor & Destructor Documentation	24
4.5.2.1 LedShift()	24
4.5.3 Member Function Documentation	25
4.5.3.1 handle()	25
4.5.3.2 set()	25
4.5.3.3 set_all()	25
4.5.3.4 setAll()	26
4.6 RepeatButton Class Reference	26
4.6.1 Detailed Description	28

4.6.2 Constructor & Destructor Documentation	28
4.6.2.1 RepeatButton() [1/2]	28
4.6.2.2 RepeatButton() [2/2]	28
4.6.3 Member Function Documentation	29
<b>4.6.3.1</b> handle() [1/2]	29
<b>4.6.3.2</b> handle() [2/2]	29
4.6.3.3 handleXP() [1/2]	29
4.6.3.4 handleXP() [2/2]	29
4.6.4 Member Data Documentation	30
4.6.4.1 _delay	30
4.6.4.2 _timer	30
4.7 Switch Class Reference	30
4.7.1 Detailed Description	31
4.7.2 Constructor & Destructor Documentation	31
<b>4.7.2.1 Switch()</b> [1/2]	31
<b>4.7.2.2 Switch()</b> [2/2]	32
4.7.3 Member Function Documentation	32
4.7.3.1 getCommand()	32
4.7.3.2 handle()	32
4.7.3.3 handleXP()	33
4.7.3.4 off()	33
4.7.3.5 on()	33
4.7.3.6 processCommand()	33
<b>4.7.3.7 setCommand()</b> [1/2]	33
<b>4.7.3.8 setCommand()</b> [2/2]	34
4.7.3.9 value()	34
4.8 Switch2 Class Reference	35
4.8.1 Detailed Description	35
4.8.2 Constructor & Destructor Documentation	35
4.8.2.1 Switch2() [1/2]	35
<b>4.8.2.2 Switch2()</b> [2/2]	36
4.8.3 Member Function Documentation	36
4.8.3.1 getCommand()	36
4.8.3.2 handle()	37
4.8.3.3 handleXP()	37
4.8.3.4 off()	37
4.8.3.5 on1()	37
4.8.3.6 on2()	38
4.8.3.7 processCommand()	38
4.8.3.8 setCommand() [1/4]	38
4.8.3.9 setCommand() [2/4]	38
4.8.3.10 setCommand() [3/4]	39

4.8.3.11 setCommand() [4/4]	39
4.8.3.12 value()	39
4.9 Timer Class Reference	40
4.9.1 Detailed Description	40
4.9.2 Constructor & Destructor Documentation	41
4.9.2.1 Timer()	41
4.9.3 Member Function Documentation	41
4.9.3.1 count()	41
4.9.3.2 elapsed()	41
4.9.3.3 getTime()	42
4.9.3.4 setCycle()	42
4.10 XPLDirect Class Reference	42
4.10.1 Detailed Description	43
4.10.2 Constructor & Destructor Documentation	43
4.10.2.1 XPLDirect()	43
4.10.3 Member Function Documentation	43
4.10.3.1 allDataRefsRegistered()	43
4.10.3.2 begin()	43
4.10.3.3 commandEnd()	44
4.10.3.4 commandStart()	44
4.10.3.5 commandTrigger() [1/2]	44
4.10.3.6 commandTrigger() [2/2]	44
4.10.3.7 connectionStatus()	44
4.10.3.8 datarefsUpdated()	45
4.10.3.9 hasUpdated()	45
4.10.3.10 registerCommand()	45
4.10.3.11 registerDataRef() [1/5]	45
<b>4.10.3.12</b> registerDataRef() [2/5]	45
<b>4.10.3.13 registerDataRef()</b> [3/5]	46
4.10.3.14 registerDataRef() [4/5]	46
<b>4.10.3.15</b> registerDataRef() [5/5]	46
4.10.3.16 sendDebugMessage()	46
4.10.3.17 sendResetRequest()	47
4.10.3.18 sendSpeakMessage()	47
4.10.3.19 xloop()	47
5 File Documentation	49
5.1 Direct inputs/main.cpp	49
5.2 MUX inputs/main.cpp	50
5.3 AnalogIn.h	50
5.4 Button.h	51
5.5 Digitalln.h	52

Inde	ex	75
!	5.19 XPLDirect.cpp	67
!	5.18 Timer.cpp	67
!	5.17 Switch.cpp	64
!	5.16 LedShift.cpp	63
!	5.15 Encoder.cpp	61
!	5.14 DigitalIn.cpp	60
!	5.13 Button.cpp	59
!	5.12 AnalogIn.cpp	58
!	5.11 XPLDirect.h	56
!	5.10 XPLDevices.h	56
!	5.9 Timer.h	55
!	5.8 Switch.h	54
!	5.7 LedShift.h	53
!	5.6 Encoder.h	53

# **Chapter 1**

# **Hierarchical Index**

# 1.1 Class Hierarchy

This inheritance list is sorted roughly, but not completely, alphabetically:

AnalogIn																					7
Button																					9
RepeatBut	ton			 																	26
DigitalIn																					16
Encoder																					18
LedShift																					24
Switch																					30
Switch2																					
Timer																					40
XPI Direct																					42

2 Hierarchical Index

# Chapter 2

# **Class Index**

# 2.1 Class List

Here are the classes, structs, unions and interfaces with brief descriptions:

Analogin		
	Class to encapsulate analog inputs	7
Button		
	Class for a simple pushbutton with debouncing and XPLDirect command handling. Supports	
	start and end of commands so XPlane can show the current Button status	9
DigitalIn_	_	
	Class to encapsulate digital inputs from 74HC4067 and MCP23017 input multiplexers, used by	10
Encoder	all digital input devices. Scans all expander inputs into internal process data image	16
Encoder		
	Class for rotary encoders with optional push functionality. The number of counts per mechanical	40
	notch can be configured for the triggering of up/down events	18
LedShift		
	Class to encapsulate a DM13A LED driver IC	24
RepeatB	utton	
	Class for a simple pushbutton with debouncing and XPLDirect command handling, supports start and end of commands so XPlane can show the current Button status. When button is held down	
	cyclic new pressed events are generated for auto repeat function	26
Switch		
	Class for a simple on/off switch with debouncing and XPLDirect command handling	30
Switch2		
	Class for an on/off/on switch with debouncing and XPLDirect command handling	35
Timer		
	Priovide a simple software driven timer for general purpose use	40
XPLDire	· · · · · · · · · · · · · · · · · · ·	42

4 Class Index

# **Chapter 3**

# File Index

# 3.1 File List

Here is a list of all documented files with brief descriptions:

Direct inputs/main.cpp	49
MUX inputs/main.cpp	50
AnalogIn.h	50
Button.h	51
DigitalIn.h	52
Encoder.h	53
LedShift.h	53
Switch.h	54
Timer.h	55
XPLDevices.h	56
XPLDirect.h	56
AnalogIn.cpp	58
Button.cpp	59
DigitalIn.cpp	60
Encoder.cpp	61
LedShift.cpp	63
Switch.cpp	64
Timer.cpp	67
XPLDirect.cpp	67

6 File Index

# **Chapter 4**

# **Class Documentation**

# 4.1 Analogin Class Reference

Class to encapsulate analog inputs.

```
#include <AnalogIn.h>
```

#### **Public Member Functions**

• AnalogIn (uint8\_t pin, Analog\_t type)

Setup analog input.

AnalogIn (uint8\_t pin, Analog\_t type, float timeConst)

Setup analog input with low pass filter.

• void handle ()

Read analog input, scale value and perform filtering, call once per sample loop.

• float value ()

Return actual value.

• int raw ()

Return raw value.

• void calibrate ()

Perform calibration for bipolar input, current position gets center and +/- ranges are adapted to cover +/-1.

#### 4.1.1 Detailed Description

Class to encapsulate analog inputs.

Definition at line 14 of file AnalogIn.h.

#### 4.1.2 Constructor & Destructor Documentation

#### 4.1.2.1 Analogin() [1/2]

Setup analog input.

#### **Parameters**

pin	Arduino pin number to use
type	unipolar (01) or bipolar (-11) range

Definition at line 7 of file AnalogIn.cpp.

#### 4.1.2.2 Analogin() [2/2]

Setup analog input with low pass filter.

#### **Parameters**

pin	Arduino pin number to use
type	unipolar (01) or bipolar (-11)
timeConst	Filter time constant (t_filter/t_sample)

Definition at line 27 of file AnalogIn.cpp.

#### 4.1.3 Member Function Documentation

#### 4.1.3.1 calibrate()

```
void AnalogIn::calibrate ( )
```

Perform calibration for bipolar input, current position gets center and +/- ranges are adapted to cover +/-1.

Definition at line 43 of file AnalogIn.cpp.

#### 4.1.3.2 handle()

```
void AnalogIn::handle ( )
```

Read analog input, scale value and perform filtering, call once per sample loop.

Definition at line 32 of file AnalogIn.cpp.

4.2 Button Class Reference 9

#### 4.1.3.3 raw()

```
int AnalogIn::raw ( )
```

Return raw value.

Returns

Read raw analog input and compensate bipolta offset

Definition at line 38 of file AnalogIn.cpp.

#### 4.1.3.4 value()

```
float AnalogIn::value ( ) [inline]
```

Return actual value.

Returns

Actual, filtered value as captured with handle()

Definition at line 33 of file AnalogIn.h.

The documentation for this class was generated from the following files:

- · AnalogIn.h
- · AnalogIn.cpp

# 4.2 Button Class Reference

Class for a simple pushbutton with debouncing and XPLDirect command handling. Supports start and end of commands so XPlane can show the current Button status.

```
#include <Button.h>
```

## **Public Member Functions**

• Button (uint8\_t mux, uint8\_t muxpin)

Constructor, set mux and pin number.

• Button (uint8\_t pin)

Constructor, set digital input without mux.

• void handle ()

Handle realtime. Read input and evaluate any transitions.

· void handle (bool input)

Handle realtime. Read input and evaluate any transitions.

• void handleXP ()

Handle realtime and process XPLDirect commands.

void handleXP (bool input)

Handle realtime and process XPLDirect commands.

• bool pressed ()

Evaluate and reset transition if button pressed down.

• bool released ()

Evaluate and reset transition if button released.

• bool engaged ()

Evaluate status of Button.

void setCommand (int cmdPush)

Set XPLDirect command for Button events.

void setCommand (XPString\_t \*cmdNamePush)

Set XPLDirect command for Button events.

• int getCommand ()

Get XPLDirect command associated with Button.

void processCommand ()

Process all transitions and active transitions to XPLDirect

### **Protected Types**

enum { transNone , transPressed , transReleased }

## **Protected Attributes**

```
uint8_t _mux
```

- uint8\_t \_pin
- uint8\_t \_state
- uint8\_t \_transition
- · int \_cmdPush

#### 4.2.1 Detailed Description

Class for a simple pushbutton with debouncing and XPLDirect command handling. Supports start and end of commands so XPlane can show the current Button status.

Definition at line 8 of file Button.h.

4.2 Button Class Reference

#### 4.2.2 Member Enumeration Documentation

#### 4.2.2.1 anonymous enum

```
anonymous enum [protected]
```

Definition at line 65 of file Button.h.

#### 4.2.3 Constructor & Destructor Documentation

### 4.2.3.1 Button() [1/2]

Constructor, set mux and pin number.

#### **Parameters**

mux	mux number (from DigitalIn initialization order)
muxpin	pin on the mux (0-15)

Definition at line 10 of file Button.cpp.

#### 4.2.3.2 Button() [2/2]

Constructor, set digital input without mux.

#### **Parameters**

pin Arduino pin number

Definition at line 21 of file Button.h.

#### 4.2.4 Member Function Documentation

#### 4.2.4.1 engaged()

```
bool Button::engaged ( ) [inline]
```

Evaluate status of **Button**.

Returns

true: Button is currently held down

Definition at line 47 of file Button.h.

#### 4.2.4.2 getCommand()

```
int Button::getCommand ( ) [inline]
```

Get XPLDirect command associated with Button.

Returns

Handle of the command

Definition at line 59 of file Button.h.

#### 4.2.4.3 handle() [1/2]

```
void Button::handle ( ) [inline]
```

Handle realtime. Read input and evaluate any transitions.

Definition at line 24 of file Button.h.

#### 4.2.4.4 handle() [2/2]

```
void Button::handle (
          bool input ) [inline]
```

Handle realtime. Read input and evaluate any transitions.

4.2 Button Class Reference 13

#### **Parameters**

*input* Additional mask bit. AND connected with physical input.

Definition at line 28 of file Button.h.

#### 4.2.4.5 handleXP() [1/2]

```
void Button::handleXP ( ) [inline]
```

Handle realtime and process XPLDirect commands.

Definition at line 31 of file Button.h.

#### 4.2.4.6 handleXP() [2/2]

```
void Button::handleXP (
                bool input ) [inline]
```

Handle realtime and process XPLDirect commands.

#### **Parameters**

*input* Additional mask bit. AND tied with physical input.

Definition at line 35 of file Button.h.

#### 4.2.4.7 pressed()

```
bool Button::pressed ( ) [inline]
```

Evaluate and reset transition if button pressed down.

#### Returns

true: Button was pressed. Transition detected.

Definition at line 39 of file Button.h.

#### 4.2.4.8 processCommand()

```
void Button::processCommand ( )
```

Process all transitions and active transitions to XPLDirect

Definition at line 50 of file Button.cpp.

#### 4.2.4.9 released()

```
bool Button::released ( ) [inline]
```

Evaluate and reset transition if button released.

Returns

true: Button was released. Transition detected.

Definition at line 43 of file Button.h.

#### 4.2.4.10 setCommand() [1/2]

Set XPLDirect command for Button events.

**Parameters** 

cmdPush | Command handle as returned by XP.registerCommand()

Definition at line 40 of file Button.cpp.

# 4.2.4.11 setCommand() [2/2]

Set XPLDirect command for Button events.

#### **Parameters**

cmdNamePush | Command name to register

4.2 Button Class Reference 15

Definition at line 45 of file Button.cpp.

#### 4.2.5 Member Data Documentation

## 4.2.5.1 \_cmdPush

```
int Button::_cmdPush [protected]
```

Definition at line 75 of file Button.h.

### 4.2.5.2 \_mux

```
uint8_t Button::_mux [protected]
```

Definition at line 71 of file Button.h.

#### 4.2.5.3 \_pin

```
uint8_t Button::_pin [protected]
```

Definition at line 72 of file Button.h.

#### 4.2.5.4 \_state

```
uint8_t Button::_state [protected]
```

Definition at line 73 of file Button.h.

#### 4.2.5.5 \_transition

```
uint8_t Button::_transition [protected]
```

Definition at line 74 of file Button.h.

The documentation for this class was generated from the following files:

- Button.h
- Button.cpp

# 4.3 Digitalln\_ Class Reference

Class to encapsulate digital inputs from 74HC4067 and MCP23017 input multiplexers, used by all digital input devices. Scans all expander inputs into internal process data image.

```
#include <DigitalIn.h>
```

#### **Public Member Functions**

• DigitalIn\_()

Class constructor.

• void setMux (uint8\_t s0, uint8\_t s1, uint8\_t s2, uint8\_t s3)

Set adress pins for 74HC4067 multiplexers. All mux share the same adress pins.

bool addMux (uint8\_t pin)

Add one 74HC4067 multiplexer.

bool getBit (uint8\_t expander, uint8\_t channel)

Get one bit from the mux or a digital input.

• void handle ()

Read all mux inputs into process data input image.

#### 4.3.1 Detailed Description

Class to encapsulate digital inputs from 74HC4067 and MCP23017 input multiplexers, used by all digital input devices. Scans all expander inputs into internal process data image.

Definition at line 24 of file DigitalIn.h.

#### 4.3.2 Constructor & Destructor Documentation

#### 4.3.2.1 Digitalln\_()

```
DigitalIn_::DigitalIn_ ( )
```

Class constructor.

Definition at line 7 of file DigitalIn.cpp.

#### 4.3.3 Member Function Documentation

#### 4.3.3.1 addMux()

Add one 74HC4067 multiplexer.

#### **Parameters**

```
pin Data pin the multiplexer is connected to
```

#### Returns

true when successful, false when all expanders have been used up (increase MUX\_MAX\_NUMBER)

Definition at line 44 of file DigitalIn.cpp.

#### 4.3.3.2 getBit()

Get one bit from the mux or a digital input.

#### **Parameters**

expander	Expander (mux or mcp) to read from. Use NOT_USED to access directly ardunio digital input	
channel	Channel (0-15) on the mux or Arduino pin when mux = NOT_USED	

#### Returns

Status of the input (inverted, true = GND, false = +5V)

Definition at line 79 of file DigitalIn.cpp.

#### 4.3.3.3 handle()

```
void DigitalIn_::handle ( )
```

Read all mux inputs into process data input image.

Definition at line 93 of file DigitalIn.cpp.

## 4.3.3.4 setMux()

Set adress pins for 74HC4067 multiplexers. All mux share the same adress pins.

#### **Parameters**

s0	Adress pin s0
s1	Adress pin s1
s2	Adress pin s2
s3	Adress pin s3

Definition at line 21 of file DigitalIn.cpp.

The documentation for this class was generated from the following files:

- · DigitalIn.h
- · DigitalIn.cpp

#### 4.4 Encoder Class Reference

Class for rotary encoders with optional push functionality. The number of counts per mechanical notch can be configured for the triggering of up/down events.

```
#include <Encoder.h>
```

#### **Public Member Functions**

Encoder (uint8\_t mux, uint8\_t pin1, uint8\_t pin2, uint8\_t pin3, EncPulse\_t pulses)

Constructor. Sets connected pins and number of counts per notch.

• Encoder (uint8\_t pin1, uint8\_t pin2, uint8\_t pin3, EncPulse\_t pulses)

Constructor. Sets connected pins and number of counts per notch.

void handle ()

Handle realtime. Read input and evaluate any transitions.

void handleXP ()

Handle realtime and process XPLDirect commands.

• int16 t pos ()

Read current Encoder count.

• bool up ()

Evaluate Encoder up one notch (positive turn) and consume event.

• bool down ()

Evaluate Encoder up down notch (negative turn) and consume event.

• bool pressed ()

Evaluate and reset transition if Encoder pressed down.

· bool released ()

Evaluate and reset transition if Encoder released.

· bool engaged ()

Evaluate status of Encoder push function.

void setCommand (int cmdUp, int cmdDown, int cmdPush)

Set XPLDirect commands for Encoder events.

• void setCommand (XPString\_t \*cmdNameUp, XPString\_t \*cmdNameDown, XPString\_t \*cmdNamePush)

Set XPLDirect commands for Encoder events.

void setCommand (int cmdUp, int cmdDown)

Set XPLDirect commands for Encoder events without push function.

void setCommand (XPString\_t \*cmdNameUp, XPString\_t \*cmdNameDown)

Set XPLDirect commands for Encoder events.

int getCommand (EncCmd\_t cmd)

Get XPLDirect command assiciated with the selected event.

void processCommand ()

Check for Encoder events and process XPLDirect commands as appropriate.

# 4.4.1 Detailed Description

Class for rotary encoders with optional push functionality. The number of counts per mechanical notch can be configured for the triggering of up/down events.

Definition at line 22 of file Encoder.h.

#### 4.4.2 Constructor & Destructor Documentation

#### 4.4.2.1 Encoder() [1/2]

Constructor. Sets connected pins and number of counts per notch.

#### **Parameters**

mux	mux number (from DigitalIn initialization order)
pin1	pin for Encoder A track
pin2	pin for Encoder B track
pin3	pin for encoder push function (NOT_USED if not connected)
pulses	Number of counts per mechanical notch

Definition at line 10 of file Encoder.cpp.

#### 4.4.2.2 Encoder() [2/2]

```
Encoder::Encoder (
            uint8_t pin1,
            uint8_t pin2,
            uint8_t pin3,
            EncPulse_t pulses ) [inline]
```

Constructor. Sets connected pins and number of counts per notch.

#### **Parameters**

pin1	pin for Encoder A track
pin2	pin for Encoder B track
pin3	pin for encoder push function (NOT_USED if not connected)
pulses	Number of counts per mechanical notch

Generated by Doxygen

Definition at line 38 of file Encoder.h.

#### 4.4.3 Member Function Documentation

#### 4.4.3.1 down()

```
bool Encoder::down ( ) [inline]
```

Evaluate Encoder up down notch (negative turn) and consume event.

Returns

true: up event available and transition reset.

Definition at line 56 of file Encoder.h.

#### 4.4.3.2 engaged()

```
bool Encoder::engaged ( ) [inline]
```

Evaluate status of **Encoder** push function.

Returns

true: Button is currently held down

Definition at line 68 of file Encoder.h.

### 4.4.3.3 getCommand()

Get XPLDirect command assiciated with the selected event.

#### **Parameters**

cmd Event to read out (encCmdUp, encCmdDown, encCmdPush)

Returns

Handle of the command, -1 = no command

Definition at line 103 of file Encoder.cpp.

#### 4.4.3.4 handle()

```
void Encoder::handle ( )
```

Handle realtime. Read input and evaluate any transitions.

Definition at line 32 of file Encoder.cpp.

#### 4.4.3.5 handleXP()

```
void Encoder::handleXP ( ) [inline]
```

Handle realtime and process XPLDirect commands.

Definition at line 44 of file Encoder.h.

#### 4.4.3.6 pos()

```
int16_t Encoder::pos ( ) [inline]
```

Read current Encoder count.

Returns

Remaining Encoder count.

Definition at line 48 of file Encoder.h.

#### 4.4.3.7 pressed()

```
bool Encoder::pressed ( ) [inline]
```

Evaluate and reset transition if Encoder pressed down.

Returns

true: Button was pressed. Transition detected and reset.

Definition at line 60 of file Encoder.h.

#### 4.4.3.8 processCommand()

```
void Encoder::processCommand ( )
```

Check for Encoder events and process XPLDirect commands as appropriate.

Definition at line 122 of file Encoder.cpp.

#### 4.4.3.9 released()

```
bool Encoder::released ( ) [inline]
```

Evaluate and reset transition if Encoder released.

#### Returns

true: Button was released. Transition detected and reset.

Definition at line 64 of file Encoder.h.

#### 4.4.3.10 setCommand() [1/4]

Set XPLDirect commands for Encoder events without push function.

#### Parameters

cmdUp	Command handle for positive turn as returned by XP.registerCommand()
cmdDown	Command handle for negative turn as returned by XP.registerCommand()

Definition at line 89 of file Encoder.cpp.

#### 4.4.3.11 setCommand() [2/4]

Set XPLDirect commands for Encoder events.

#### **Parameters**

cmdUp	Command handle for positive turn as returned by XP.registerCommand()	
cmdDown	Command handle for negative turn as returned by XP.registerCommand()	
cmdPush	Command handle for push as returned by XP.registerCommand()	

Definition at line 75 of file Encoder.cpp.

#### 4.4.3.12 setCommand() [3/4]

Set XPLDirect commands for Encoder events.

#### **Parameters**

cmdNameUp	Command for positive turn
cmdNameDown	Command for negative turn

Definition at line 96 of file Encoder.cpp.

#### 4.4.3.13 setCommand() [4/4]

Set XPLDirect commands for Encoder events.

#### **Parameters**

cmdNameUp	Command for positive turn
cmdNameDown	Command for negative turn
cmdNamePush	Command for push

Definition at line 82 of file Encoder.cpp.

#### 4.4.3.14 up()

```
bool Encoder::up ( ) [inline]
```

Evaluate Encoder up one notch (positive turn) and consume event.

Returns

true: up event available and transition reset.

Definition at line 52 of file Encoder.h.

The documentation for this class was generated from the following files:

- · Encoder.h
- · Encoder.cpp

#### 4.5 LedShift Class Reference

Class to encapsulate a DM13A LED driver IC.

```
#include <LedShift.h>
```

#### **Public Member Functions**

```
    LedShift (uint8_t pin_DAI, uint8_t pin_DCK, uint8_t pin_LAT)
    Constructor, setup DM13A LED driver and set pins.
```

void set (uint8\_t pin, led\_t mode)

Set one LED to a display mode.

void setAll (led\_t mode)

Set display mode for all 16 LEDs.

void set\_all (led\_t mode)

Set display mode for all 16 LEDs (obsolete, replaced by setAll())

• void handle ()

Real time handling, call cyclic in loop()

### 4.5.1 Detailed Description

Class to encapsulate a DM13A LED driver IC.

Definition at line 21 of file LedShift.h.

#### 4.5.2 Constructor & Destructor Documentation

#### 4.5.2.1 LedShift()

Constructor, setup DM13A LED driver and set pins.

#### **Parameters**

pin_DAI	DAI pin of DM13A
pin_DCK	DCL pin of DM13A
pin_LAT	LAT pin of DM13A

Definition at line 6 of file LedShift.cpp.

#### 4.5.3 Member Function Documentation

#### 4.5.3.1 handle()

```
void LedShift::handle ( )
```

Real time handling, call cyclic in loop()

Definition at line 88 of file LedShift.cpp.

#### 4.5.3.2 set()

```
void LedShift::set (
          uint8_t pin,
          led_t mode )
```

Set one LED to a display mode.

### Parameters

pin	DM13A pin of the LED (0-15)
mode	LED display mode

Definition at line 71 of file LedShift.cpp.

#### 4.5.3.3 set\_all()

Set display mode for all 16 LEDs (obsolete, replaced by setAll())

#### **Parameters**

mode	LED display mode
------	------------------

Definition at line 41 of file LedShift.h.

#### 4.5.3.4 setAll()

Set display mode for all 16 LEDs.

#### **Parameters**

mode   LED display mode
-------------------------

Definition at line 78 of file LedShift.cpp.

The documentation for this class was generated from the following files:

- · LedShift.h
- · LedShift.cpp

# 4.6 RepeatButton Class Reference

Class for a simple pushbutton with debouncing and XPLDirect command handling, supports start and end of commands so XPlane can show the current Button status. When button is held down cyclic new pressed events are generated for auto repeat function.

```
#include <Button.h>
```

#### **Public Member Functions**

• RepeatButton (uint8\_t mux, uint8\_t muxpin, uint32\_t delay)

Constructor, set mux and pin number.

• RepeatButton (uint8\_t pin, uint32\_t delay)

Constructor, set digital input without mux.

• void handle ()

Handle realtime. Read input and evaluate any transitions.

• void handle (bool input)

Handle realtime. Read input and evaluate any transitions.

• void handleXP ()

Handle realtime and process XPLDirect commands.

void handleXP (bool input)

Handle realtime and process XPLDirect commands.

#### **Public Member Functions inherited from Button**

• Button (uint8\_t mux, uint8\_t muxpin)

Constructor, set mux and pin number.

• Button (uint8\_t pin)

Constructor, set digital input without mux.

• void handle ()

Handle realtime. Read input and evaluate any transitions.

· void handle (bool input)

Handle realtime. Read input and evaluate any transitions.

• void handleXP ()

Handle realtime and process XPLDirect commands.

void handleXP (bool input)

Handle realtime and process XPLDirect commands.

• bool pressed ()

Evaluate and reset transition if button pressed down.

• bool released ()

Evaluate and reset transition if button released.

• bool engaged ()

Evaluate status of Button.

void setCommand (int cmdPush)

Set XPLDirect command for Button events.

void setCommand (XPString\_t \*cmdNamePush)

Set XPLDirect command for Button events.

• int getCommand ()

Get XPLDirect command associated with Button.

void processCommand ()

Process all transitions and active transitions to XPLDirect

#### **Protected Attributes**

- · uint32\_t \_delay
- uint32 t timer

#### **Protected Attributes inherited from Button**

- uint8\_t \_mux
- uint8\_t \_pin
- uint8\_t \_state
- uint8\_t \_transition
- int \_cmdPush

# **Additional Inherited Members**

#### **Protected Types inherited from Button**

enum { transNone , transPressed , transReleased }

## 4.6.1 Detailed Description

Class for a simple pushbutton with debouncing and XPLDirect command handling, supports start and end of commands so XPlane can show the current Button status. When button is held down cyclic new pressed events are generated for auto repeat function.

Definition at line 81 of file Button.h.

#### 4.6.2 Constructor & Destructor Documentation

#### 4.6.2.1 RepeatButton() [1/2]

```
RepeatButton::RepeatButton (
uint8_t mux,
uint8_t muxpin,
uint32_t delay )
```

Constructor, set mux and pin number.

#### **Parameters**

mux	mux number (from initialization order)
muxpin	pin on the mux (0-15)
delay	Cyclic delay for repeat function

Definition at line 62 of file Button.cpp.

### 4.6.2.2 RepeatButton() [2/2]

Constructor, set digital input without mux.

#### **Parameters**

pin	Arduino pin number
delay	Cyclic delay for repeat function

Definition at line 96 of file Button.h.

# 4.6.3 Member Function Documentation

# 4.6.3.1 handle() [1/2]

```
void RepeatButton::handle ( ) [inline]
```

Handle realtime. Read input and evaluate any transitions.

Definition at line 99 of file Button.h.

# 4.6.3.2 handle() [2/2]

```
void RepeatButton::handle (
          bool input ) [inline]
```

Handle realtime. Read input and evaluate any transitions.

### **Parameters**

input Additional mask bit. AND connected with physical input.

Definition at line 103 of file Button.h.

# 4.6.3.3 handleXP() [1/2]

```
void RepeatButton::handleXP ( ) [inline]
```

Handle realtime and process XPLDirect commands.

Definition at line 106 of file Button.h.

### 4.6.3.4 handleXP() [2/2]

```
void RepeatButton::handleXP (
          bool input ) [inline]
```

Handle realtime and process XPLDirect commands.

### **Parameters**

*input* Additional mask bit. AND tied with physical input.

Definition at line 110 of file Button.h.

# 4.6.4 Member Data Documentation

# 4.6.4.1 \_delay

```
uint32_t RepeatButton::_delay [protected]
```

Definition at line 113 of file Button.h.

### 4.6.4.2 timer

```
uint32_t RepeatButton::_timer [protected]
```

Definition at line 114 of file Button.h.

The documentation for this class was generated from the following files:

- Button.h
- Button.cpp

# 4.7 Switch Class Reference

Class for a simple on/off switch with debouncing and XPLDirect command handling.

```
#include <Switch.h>
```

4.7 Switch Class Reference 31

### **Public Member Functions**

• Switch (uint8\_t mux, uint8\_t pin)

Constructor. Connect the switch to a pin on a mux.

Switch (uint8\_t pin)

Constructor, set digital input without mux.

• void handle ()

Handle realtime. Read input and evaluate any transitions.

• void handleXP ()

Handle realtime and process XPLDirect commands.

• bool on ()

Check whether Switch set to on.

• bool off ()

Check whether Switch set to off.

void setCommand (int cmdOn, int cmdOff)

Set XPLDirect commands for Switch events.

void setCommand (XPString\_t \*cmdNameOn, XPString\_t \*cmdNameOff)

Set XPLDirect commands for Switch events.

• int getCommand ()

Get XPLDirect command for last transition of Switch.

void processCommand ()

Process all transitions to XPLDirect.

float value (float onValue, float offValue)

Check Status of Switch and translate to float value.

# 4.7.1 Detailed Description

Class for a simple on/off switch with debouncing and XPLDirect command handling.

Definition at line 7 of file Switch.h.

### 4.7.2 Constructor & Destructor Documentation

### 4.7.2.1 Switch() [1/2]

Constructor. Connect the switch to a pin on a mux.

### **Parameters**

mux	mux number (from DigitalIn initialization order)
muxpin	pin on the mux (0-15)

Definition at line 9 of file Switch.cpp.

### 4.7.2.2 Switch() [2/2]

Constructor, set digital input without mux.

### **Parameters**

pin	Arduino pin number
-----	--------------------

Definition at line 17 of file Switch.h.

# 4.7.3 Member Function Documentation

# 4.7.3.1 getCommand()

```
int Switch::getCommand ( )
```

Get XPLDirect command for last transition of Switch.

Returns

Handle of the last command

Definition at line 53 of file Switch.cpp.

# 4.7.3.2 handle()

```
void Switch::handle ( )
```

Handle realtime. Read input and evaluate any transitions.

Definition at line 19 of file Switch.cpp.

4.7 Switch Class Reference 33

### 4.7.3.3 handleXP()

```
void Switch::handleXP ( ) [inline]
```

Handle realtime and process XPLDirect commands.

Definition at line 23 of file Switch.h.

### 4.7.3.4 off()

```
bool Switch::off ( ) [inline]
```

Check whether Switch set to off.

Returns

true: Switch is off

Definition at line 31 of file Switch.h.

### 4.7.3.5 on()

```
bool Switch::on ( ) [inline]
```

Check whether Switch set to on.

Returns

true: Switch is on

Definition at line 27 of file Switch.h.

# 4.7.3.6 processCommand()

```
void Switch::processCommand ( )
```

Process all transitions to XPLDirect.

Definition at line 69 of file Switch.cpp.

### 4.7.3.7 setCommand() [1/2]

Set XPLDirect commands for Switch events.

### **Parameters**

cmdOn	Command handle for Switch moved to on as returned by XP.registerCommand()
cmdOff	Command handle for Switch moved to off as returned by XP.registerCommand()

Definition at line 41 of file Switch.cpp.

# 4.7.3.8 setCommand() [2/2]

Set XPLDirect commands for Switch events.

### **Parameters**

	Command for Switch moved to on
cmdNameOff	Command for Switch moved to off

Definition at line 47 of file Switch.cpp.

### 4.7.3.9 value()

Check Status of Switch and translate to float value.

#### **Parameters**

onValue	Value to return when Switch is set to on
offValue	Value to return when Switch is set to off

# Returns

Returned value

Definition at line 54 of file Switch.h.

The documentation for this class was generated from the following files:

- Switch.h
- Switch.cpp

### 4.8 Switch2 Class Reference

Class for an on/off/on switch with debouncing and XPLDirect command handling.

```
#include <Switch.h>
```

### **Public Member Functions**

• Switch2 (uint8\_t mux, uint8\_t pin1, uint8\_t pin2)

Constructor. Connect the switch to pins on a mux.

Switch2 (uint8\_t pin1, uint8\_t pin2)

Constructor, set digital input pins without mux.

• void handle ()

Handle realtime. Read inputs and evaluate any transitions.

void handleXP ()

Handle realtime and process XPLDirect commands.

bool off ()

Check whether Switch set to off.

• bool on1 ()

Check whether Switch set to on1.

• bool on2 ()

Check whether Switch set to on2.

void setCommand (int cmdUp, int cmdDown)

Set XPLDirect commands for Switch events in cases only up/down commands are to be used.

void setCommand (XPString t \*cmdNameUp, XPString t \*cmdNameDown)

Set XPLDirect commands for Switch events in cases only up/down commands are to be used.

void setCommand (int cmdOn1, int cmdOff, int cmdOn2)

Set XPLDirect commands for Switch events in cases separate events for on1/off/on2 are to be used.

void setCommand (XPString\_t \*cmdNameOn1, XPString\_t \*cmdNameOff, XPString\_t \*cmdNameOn2)

Set XPLDirect commands for Switch events in cases separate events for on1/off/on2 are to be used.

• int getCommand ()

Get XPLDirect command for last transition of Switch.

void processCommand ()

Process all transitions to XPLDirect.

• float value (float on1 Value, float off Value, float on2 value)

Check Status of Switch and translate to float value.

# 4.8.1 Detailed Description

Class for an on/off/on switch with debouncing and XPLDirect command handling.

Definition at line 72 of file Switch.h.

# 4.8.2 Constructor & Destructor Documentation

### 4.8.2.1 Switch2() [1/2]

Constructor. Connect the switch to pins on a mux.

### **Parameters**

mux	mux number (from DigitalIn initialization order)
pin1	on1 pin on the mux (0-15)
pin1	on2 pin on the mux (0-15)

Definition at line 80 of file Switch.cpp.

# 4.8.2.2 Switch2() [2/2]

Constructor, set digital input pins without mux.

### **Parameters**

pin1	on1 Arduino pin number
pin2	on2 Arduino pin number

Definition at line 84 of file Switch.h.

# 4.8.3 Member Function Documentation

# 4.8.3.1 getCommand()

```
int Switch2::getCommand ( )
```

Get XPLDirect command for last transition of Switch.

### Returns

Handle of the last command

Definition at line 151 of file Switch.cpp.

# 4.8.3.2 handle()

```
void Switch2::handle ( )
```

Handle realtime. Read inputs and evaluate any transitions.

Definition at line 96 of file Switch.cpp.

# 4.8.3.3 handleXP()

```
void Switch2::handleXP ( ) [inline]
```

Handle realtime and process XPLDirect commands.

Definition at line 90 of file Switch.h.

### 4.8.3.4 off()

```
bool Switch2::off ( ) [inline]
```

Check whether Switch set to off.

Returns

true: Switch is off

Definition at line 94 of file Switch.h.

### 4.8.3.5 on1()

```
bool Switch2::on1 ( ) [inline]
```

Check whether Switch set to on1.

Returns

true: Switch is on1

Definition at line 98 of file Switch.h.

### 4.8.3.6 on2()

```
bool Switch2::on2 ( ) [inline]
```

Check whether Switch set to on2.

Returns

true: Switch is on2

Definition at line 102 of file Switch.h.

### 4.8.3.7 processCommand()

```
void Switch2::processCommand ( )
```

Process all transitions to XPLDirect.

Definition at line 190 of file Switch.cpp.

### 4.8.3.8 setCommand() [1/4]

Set XPLDirect commands for Switch events in cases separate events for on1/off/on2 are to be used.

### **Parameters**

cmdOn1	Command handle for Switch moved to on1 position as returned by XP.registerCommand()
cmdOff Command handle for Switch moved to off position as returned by XP.register	
cmdOn2	Command handle for Switch moved to on2 position as returned by XP.registerCommand()

Definition at line 137 of file Switch.cpp.

# 4.8.3.9 setCommand() [2/4]

Set XPLDirect commands for Switch events in cases only up/down commands are to be used.

#### **Parameters**

cmdUp	Command handle for Switch moved from on1 to off or from off to on2 as returned by XP.registerCommand()
cmdDown	Command handle for Switch moved from on2 to off or from off to on1 as returned by XP.registerCommand()

Definition at line 123 of file Switch.cpp.

### 4.8.3.10 setCommand() [3/4]

Set XPLDirect commands for Switch events in cases separate events for on1/off/on2 are to be used.

#### **Parameters**

cmdNameOn1	Command for Switch moved to on1 position
cmdNameOff	Command for Switch moved to off position
cmdNameOn2	Command for Switch moved to on2 position

Definition at line 144 of file Switch.cpp.

### 4.8.3.11 setCommand() [4/4]

Set XPLDirect commands for Switch events in cases only up/down commands are to be used.

#### **Parameters**

cmdNameUp	Command for Switch moved from on1 to off or from off to on2 on
cmdNameDown	Command for Switch moved from on2 to off or from off to on1

Definition at line 130 of file Switch.cpp.

### 4.8.3.12 value()

```
float Switch2::value (
```

```
float on1Value,
float offValue,
float on2value ) [inline]
```

Check Status of Switch and translate to float value.

### **Parameters**

on1 Value	Value to return when Switch is set to on1
offValue	Value to return when Switch is set to off
on2Value	Value to return when Switch is set to on2

### Returns

Returned value

Definition at line 138 of file Switch.h.

The documentation for this class was generated from the following files:

- · Switch.h
- · Switch.cpp

# 4.9 Timer Class Reference

Priovide a simple software driven timer for general purpose use.

```
#include <Timer.h>
```

### **Public Member Functions**

• Timer (float cycle=0)

Setup timer.

• void setCycle (float cycle)

Set or reset cycle time.

• bool elapsed ()

Check if cyclic timer elapsed and reset if so.

• float getTime ()

Get measured time since and reset timer.

• long count ()

Return cycle counter and reset to zero.

# 4.9.1 Detailed Description

Priovide a simple software driven timer for general purpose use.

Definition at line 6 of file Timer.h.

4.9 Timer Class Reference 41

# 4.9.2 Constructor & Destructor Documentation

# 4.9.2.1 Timer()

Setup timer.

**Parameters** 

cycle | Cycle time for elapsing timer in ms. 0 means no cycle, just for measurement.

Definition at line 4 of file Timer.cpp.

### 4.9.3 Member Function Documentation

### 4.9.3.1 count()

```
long Timer::count ( )
```

Return cycle counter and reset to zero.

Returns

Number of calls to elapsed() since last call of count()

Definition at line 35 of file Timer.cpp.

# 4.9.3.2 elapsed()

```
bool Timer::elapsed ( )
```

Check if cyclic timer elapsed and reset if so.

Returns

true: timer elapsed and restarted, false: still running

Definition at line 15 of file Timer.cpp.

### 4.9.3.3 getTime()

```
float Timer::getTime ( )
```

Get measured time since and reset timer.

Returns

Elapsed time in ms

Definition at line 27 of file Timer.cpp.

### 4.9.3.4 setCycle()

Set or reset cycle time.

**Parameters** 

cycle | Cycle time in ms

Definition at line 10 of file Timer.cpp.

The documentation for this class was generated from the following files:

- Timer.h
- · Timer.cpp

# 4.10 XPLDirect Class Reference

### **Public Member Functions**

- XPLDirect (Stream \*)
- void begin (const char \*devicename)
- int connectionStatus (void)
- int commandTrigger (int commandHandle)
- int commandTrigger (int commandHandle, int triggerCount)
- int commandStart (int commandHandle)
- int commandEnd (int commandHandle)
- int datarefsUpdated ()
- int hasUpdated (int handle)
- int registerDataRef (XPString\_t \*datarefName, int rwmode, unsigned int rate, float divider, long int \*value)
- int registerDataRef (XPString\_t \*datarefName, int rwmode, unsigned int rate, float divider, long int \*value, int index)
- int registerDataRef (XPString\_t \*datarefName, int rwmode, unsigned int rate, float divider, float \*value)

- int registerDataRef (XPString\_t \*datarefName, int rwmode, unsigned int rate, float divider, float \*value, int index)
- int registerDataRef (XPString\_t \*datarefName, int rwmode, unsigned int rate, char \*value)
- int registerCommand (XPString\_t \*commandName)
- int sendDebugMessage (const char \*msg)
- int sendSpeakMessage (const char \*msg)
- int allDataRefsRegistered (void)
- void sendResetRequest (void)
- int xloop (void)

# 4.10.1 Detailed Description

Definition at line 81 of file XPLDirect.h.

### 4.10.2 Constructor & Destructor Documentation

# 4.10.2.1 XPLDirect()

Definition at line 11 of file XPLDirect.cpp.

# 4.10.3 Member Function Documentation

# 4.10.3.1 allDataRefsRegistered()

Definition at line 458 of file XPLDirect.cpp.

### 4.10.3.2 begin()

Definition at line 17 of file XPLDirect.cpp.

### 4.10.3.3 commandEnd()

Definition at line 129 of file XPLDirect.cpp.

# 4.10.3.4 commandStart()

Definition at line 111 of file XPLDirect.cpp.

### 4.10.3.5 commandTrigger() [1/2]

Definition at line 72 of file XPLDirect.cpp.

# 4.10.3.6 commandTrigger() [2/2]

Definition at line 90 of file XPLDirect.cpp.

# 4.10.3.7 connectionStatus()

Definition at line 147 of file XPLDirect.cpp.

# 4.10.3.8 datarefsUpdated()

```
int XPLDirect::datarefsUpdated ( )
```

Definition at line 174 of file XPLDirect.cpp.

# 4.10.3.9 hasUpdated()

Definition at line 164 of file XPLDirect.cpp.

# 4.10.3.10 registerCommand()

Definition at line 566 of file XPLDirect.cpp.

### 4.10.3.11 registerDataRef() [1/5]

Definition at line 546 of file XPLDirect.cpp.

# 4.10.3.12 registerDataRef() [2/5]

Definition at line 505 of file XPLDirect.cpp.

### 4.10.3.13 registerDataRef() [3/5]

Definition at line 526 of file XPLDirect.cpp.

# 4.10.3.14 registerDataRef() [4/5]

Definition at line 463 of file XPLDirect.cpp.

# 4.10.3.15 registerDataRef() [5/5]

Definition at line 484 of file XPLDirect.cpp.

### 4.10.3.16 sendDebugMessage()

Definition at line 152 of file XPLDirect.cpp.

# 4.10.3.17 sendResetRequest()

```
\begin{tabular}{ll} \beg
```

Definition at line 200 of file XPLDirect.cpp.

# 4.10.3.18 sendSpeakMessage()

Definition at line 158 of file XPLDirect.cpp.

### 4.10.3.19 xloop()

```
int XPLDirect::xloop (
     void )
```

Definition at line 27 of file XPLDirect.cpp.

The documentation for this class was generated from the following files:

- XPLDirect.h
- XPLDirect.cpp

# **Chapter 5**

# **File Documentation**

# 5.1 Direct inputs/main.cpp

```
00001 #include <Arduino.h>
00002 #include <XPLDevices.h>
00003
00004 // The XPLDirect library is automatically installed by PlatformIO with XPLDevices 00005 // Optional defines for XPLDirect can be set in platformio.ini
00006 // This sample contains all the important defines. Modify or remove as needed
00008 // A simple Pushbutton on Arduino pin 2
00009 Button btnStart(2);
00010
00011 // An Encoder with push functionality. 3\&4 are the encoder pins, 5 the push pin. 00012 // configured for an Encoder with 4 counts per mechanical notch, which is the standard
00013 Encoder encHeading(3, 4, 5, enc4Pulse);
00015 // A simple On/Off switch on pin 6
00016 Switch swStrobe(6);
00017
00018 // A Variable to be connected to a DataRef
00019 long strobe;
00021 // Arduino setup function, called once
00022 void setup() {
00023 // setup interface
        Serial.begin(XPLDIRECT_BAUDRATE);
00024
00025
        XP.begin("Sample");
00026
00027
         // Register Command for the Button
00028
        btnStart.setCommand(
             XP.registerCommand(F("sim/starters/engage_starter_1")));
00029
00030
00031
         // Register Commands for Encoder Up/Down/Push function.
00032
         encHeading.setCommand(
00033
          XP.registerCommand(F("sim/autopilot/heading_up")),
           XP.registerCommand(F("sim/autopilot/heading_down")),
XP.registerCommand(F("sim/autopilot/heading_sync")));
00034
00035
00036
00037
         // Gegister Commands for Switch On and Off transitions. Commands are sent when Switch is moved
00038
         swStrobe.setCommand(
00039
              XP.registerCommand(F("sim/lights/strobe_lights_on")),
00040
              XP.registerCommand(F("sim/lights/strobe_lights_off")));
00041
         // Register a DataRef for the strobe light. Read only from XP, 100ms minimum Cycle time, no divider XP.registerDataRef(F("sim/cockpit/electrical/strobe_lights_on"), XPL_READ, 100, 0, &strobe);
00042
00043
00044 }
00046 // Arduino loop function, called cyclic
00047 void loop() {
        // Handle XPlane interface
00048
00049
        XP.xloop();
00050
         // handle all devices and automatically process commandsin background
00052
        btnStart.handleXP();
00053
         encHeading.handleXP();
00054
        swStrobe.handleXP();
00055
00056
         // Show the status of the Strobe on the internal LED
00057
        digitalWrite(LED_BUILTIN, (strobe > 0));
00058 }
```

# 5.2 MUX inputs/main.cpp

```
00001 #include <Arduino.h>
00002 #include <XPLDevices.h>
00003
00004 //
         The XPLDirect library is automatically installed by PlatformIO with XPLDevices
00005 // Optional defines for XPLDirect can be set in platformio.ini
00006 // This sample contains all the important defines. Modify or remove as needed
00007
00008 // This sample shows how to use 74HC4067 Multiplexers for the inputs as commonly used by SimVim
00009
00010 // A simple Pushbutton on MUX0 pin 0 \,
00011 Button btnStart(0, 0);
00013 // An Encoder with push functionality. MUX1 pin 8\&9 are the encoder pins, 10 the push pin.
00014 // configured for an Encoder with 4 counts per mechanical notch, which is the standard
00015 Encoder encHeading(1, 8, 9, 10, enc4Pulse);
00016
00017 // A simple On/Off switch on MUX0, pin 15
00018 Switch swStrobe(0, 15);
00019
00020 // A Variable to be connected to a DataRef
00021 long strobe;
00022
00023 // Arduino setup function, called once
00024 void setup() {
00025
      // setup interface
00026
        Serial.begin(XPLDIRECT_BAUDRATE);
00027
        XP.begin("Sample");
00028
        // Connect MUX adress pins to Pin 22-25 (SimVim Pins)
00029
        DigitalIn.setMux(22, 23, 24, 25);
00031
        // Logical MUX0 on Pin 38
00032
        DigitalIn.addMux(38);
00033
        // Logical MUX1 on Pin 39
00034
        DigitalIn.addMux(39);
00035
00036
        // Register Command for the Button
00037
        btnStart.setCommand(
00038
            XP.registerCommand(F("sim/starters/engage_starter_1")));
00039
00040
        // Register Commands for Encoder Up/Down/Push function.
00041
        encHeading.setCommand(
          XP.registerCommand(F("sim/autopilot/heading_up")),
00042
00043
          XP.registerCommand(F("sim/autopilot/heading_down"
00044
          XP.registerCommand(F("sim/autopilot/heading_sync")));
00045
00046
        // Gegister Commands for Switch On and Off transitions. Commands are sent when Switch is moved
00047
        swStrobe.setCommand(
00048
            XP.registerCommand(F("sim/lights/strobe_lights_on")),
00049
            XP.registerCommand(F("sim/lights/strobe_lights_off")));
00050
        // Register a DataRef for the strobe light. Read only from XP, 100ms minimum Cycle time, no divider XP.registerDataRef(F("sim/cockpit/electrical/strobe_lights_on"), XPL_READ, 100, 0, &strobe);
00051
00052
00053 }
00054
00055 // Arduino loop function, called cyclic
00056 void loop() {
00057
       // Handle XPlane interface
00058
       XP.xloop();
00059
00060
        // handle all devices and automatically process commands in background
       btnStart.handleXP();
00062
        encHeading.handleXP();
00063
        swStrobe.handleXP();
00064
        // Show the status of the Strobe on the internal LED
00065
00066
       digitalWrite(LED_BUILTIN, (strobe > 0));
00067 }
```

# 5.3 Analogin.h

```
00001 #ifndef AnalogIn_h
00002 #define AnalogIn_h
00003 #include <Arduino.h>
00004
00005 #define AD_RES 10
00006
00007 enum Analog_t
00008 {
00009 unipolar,
00010 bipolar
00011 };
```

5.4 Button.h 51

```
00012
00014 class AnalogIn
00015 {
00016 public:
00020
        AnalogIn(uint8_t pin, Analog_t type);
00021
        AnalogIn(uint8_t pin, Analog_t type, float timeConst);
00027
00029
        void handle();
00030
        float value() { return _value; };
00033
00034
00037
        int raw();
00038
00040
        void calibrate();
00041
00042 private:
        float _filterConst;
float _value;
00043
00044
        float _scale;
float _scalePos;
float _scaleNeg;
00045
00046
00047
00048
        int _offset;
        uint8_t _pin;
00049
00050 };
00052 #endif
```

# 5.4 Button.h

```
00001 #ifndef Button h
00002 #define Button_h
00003 #include <Arduino.h>
00004 #include <DigitalIn.h>
00005
00008 class Button
00009 {
00010 private:
00011
       void _handle(bool input);
00012
00013 public:
00017
       Button(uint8_t mux, uint8_t muxpin);
00018
00021
       Button(uint8_t pin) : Button(NOT_USED, pin){};
00022
00024
       void handle()
                                      { _handle(true); };
00025
00028
       void handle(bool input)
                                     { _handle(input); };
00029
                                      { _handle(true); processCommand(); };
00031
       void handleXP()
00032
       void handleXP(bool input)
                                     { _handle(input); processCommand(); };
00036
00039
       bool pressed()
                                      { return _transition == transPressed ? (_transition = transNone,
     true) : false; };
00040
00043
       bool released()
                                      { return _transition == transReleased ? (_transition = transNone,
      true) : false; };
00044
00047
       bool engaged()
                                      { return _state > 0; };
00048
00051
       void setCommand(int cmdPush);
00052
00055
       void setCommand(XPString_t *cmdNamePush);
00056
00059
       int getCommand()
                                     { return _cmdPush; };
00060
00062
       void processCommand();
00063
00064 protected:
00065
       enum
00066
00067
         transNone,
00068
         transPressed,
00069
         transReleased
00070
00071
       uint8_t _mux;
00072
        uint8_t _pin;
00073
        uint8_t _state;
00074
        uint8_t _transition;
00075
       int _cmdPush;
00076 };
00077
```

```
00081 class RepeatButton : public Button
00082 {
00083 private:
00084
       void _handle(bool input);
00085
00086 public:
       RepeatButton(uint8_t mux, uint8_t muxpin, uint32_t delay);
00092
00096
       RepeatButton(uint8_t pin, uint32_t delay) : RepeatButton(NOT_USED, pin, delay) {};
00097
00099
       void handle()
                                      { _handle(true); };
00100
00103
       void handle(bool input)
                                      { handle(input); };
00104
00106
       void handleXP()
                                      { _handle(true); processCommand(); };
00107
       void handleXP (bool input)
                                     { _handle(input); processCommand(); };
00110
00111
00112 protected:
       uint32_t _delay;
00113
00114
       uint32_t _timer;
00115 };
00116
00117 #endif
```

# 5.5 Digitalln.h

```
00001 #ifndef DigitalIn_h
00002 #define DigitalIn_h
00003 #include <Arduino.h>
00004
00006 #ifndef MUX_MAX_NUMBER
00007 #define MUX_MAX_NUMBER 6
00008 #endif
00009
00011 #ifndef MCP_MAX_NUMBER
00012 #define MCP_MAX_NUMBER 0
00013 #endif
00014
00015 // Include i2c lib only when needed
00016 #if MCP_MAX_NUMBER > 0
00017 #include <Adafruit_MCP23X17.h>
00018 #endif
00019
00020 #define NOT_USED 255
00021
00024 class DigitalIn_
00025 {
00026 public:
00028
       DigitalIn_();
00029
       void setMux(uint8_t s0, uint8_t s1, uint8_t s2, uint8_t s3);
00036
00040 bool addMux(uint8_t pin);
00041
00042 #if MCP_MAX_NUMBER > 0
00046 bool addMCP(uint8_t adress);
00047 #endif
00048
00053
       bool getBit(uint8_t expander, uint8_t channel);
00054
00056
       void handle();
00057 private:
00062 #endif
00063 uint8_t _numPins;
       uint8_t _pin[MUX_MAX_NUMBER + MCP_MAX_NUMBER];
int16_t _data[MUX_MAX_NUMBER + MCP_MAX_NUMBER];
00064
00066 #if MCP_MAX_NUMBER >
Adafruit_MCP23X17 _mcp[MCP_MAX_NUMBER];
00069 #endif
00070 };
00071
00073 extern DigitalIn_ DigitalIn;
00074
00075 #endif
```

5.6 Encoder.h 53

# 5.6 Encoder.h

```
00001 #ifndef Encoder_h
00002 #define Encoder_h
00003 #include <Arduino.h>
00004 #include <DigitalIn.h>
00005
00006 enum EncCmd_t
00007 {
80000
        encCmdUp,
00009
        encCmdDown.
00010
        encCmdPush
00011 };
00012
00013 enum EncPulse_t
00014 {
00015
        enc1Pulse = 1.
        enc2Pulse = 2.
00016
00017
        enc4Pulse = 4
00018 };
00019
00022 class Encoder
00023 {
00024 public:
00031
        Encoder(uint8_t mux, uint8_t pin1, uint8_t pin2, uint8_t pin3, EncPulse_t pulses);
00032
        Encoder(uint8_t pin1, uint8_t pin2, uint8_t pin3, EncPulse_t pulses) : Encoder(NOT_USED, pin1, pin2,
pin3, pulses) {}

00039
00041
        void handle();
00042
        void handleXP()
                          { handle(); processCommand(); };
00045
00048
        int16_t pos()
                           { return _count; };
00049
                           { return _count >= _pulses ? (_count -= _pulses, true) : false; };
        bool up()
00053
00056
        bool down()
                           { return _count <= -_pulses ? (_count += _pulses, true) : false; };
00057
00060
        bool pressed()
                           { return _transition == transPressed ? (_transition = transNone, true) : false;
00061
                           { return _transition == transReleased ? (_transition = transNone, true) : false;
00064
        bool released()
      };
00065
00068
                           { return _state > 0; };
        bool engaged()
00069
00074
        void setCommand(int cmdUp, int cmdDown, int cmdPush);
00075
08000
        void setCommand (XPString t *cmdNameUp, XPString t *cmdNameDown, XPString t *cmdNamePush);
00081
00085
        void setCommand(int cmdUp, int cmdDown);
00086
00090
        void setCommand(XPString_t *cmdNameUp, XPString_t *cmdNameDown);
00091
00095
        int getCommand(EncCmd_t cmd);
00096
00098
        void processCommand();
00099 private:
00100 enum
00101
00102
          transNone,
00103
          transPressed,
00104
          transReleased
00105
00106
        uint8_t _mux;
        uint8_t _pin1, _pin2, _pin3;
00107
        int8_t _count;
uint8_t _pulses;
uint8_t _state;
00108
00109
00110
00111
        uint8_t _debounce;
00112
        uint8_t _transition;
00113
        int _cmdUp;
00114
        int _cmdDown;
00115
        int cmdPush;
00116 };
00117
00118 #endif
```

# 5.7 LedShift.h

```
00001 #ifndef LedShift_h
00002 #define LedShift_h
```

```
00003 #include <Arduino.h>
00004
00006 enum led_t
00007 {
00009
        ledOff.
00011
        ledSlow,
00013
        ledMedium,
00015
        ledFast,
00017
       led0n
00018 };
00019
00021 class LedShift
00022 {
00023 public:
00028
        LedShift(uint8_t pin_DAI, uint8_t pin_DCK, uint8_t pin_LAT);
00029
        void set(uint8_t pin, led_t mode);
00033
00034
00037
        void setAll(led_t mode);
00038
00041
        void set_all(led_t mode) { setAll(mode); };
00042
00044
        void handle();
00045
00046 private:
00047
        void _send();
void _set(uint8_t pin);
00048
00049
        uint8_t _pin_DAI;
00050
        uint8_t _pin_DCK;
        uint8_t _pin_LAT;
uint16_t _state;
00051
00052
        led_t _mode[16];
uint8_t _count;
00053
00054
00055
        unsigned long _timer;
00056
        bool _update;
00057 };
00058
00059 #endif
```

### 5.8 Switch.h

```
00001 #ifndef Switch h
00002 #define Switch_h
00003 #include <Arduino.h>
00004 #include <DigitalIn.h>
00005
00007 class Switch
00008 {
00009 public:
00013
        Switch (uint8 t mux, uint8 t pin);
00014
00017
        Switch(uint8_t pin) : Switch (NOT_USED, pin) {};
00018
00020
       void handle();
00021
        void handleXP() { handle(); processCommand(); };
00023
00024
00027
        bool on()
                         { return _state == switchOn; };
00028
00031
        bool off()
                         { return _state == switchOff; };
00032
00036
        void setCommand(int cmdOn, int cmdOff);
00037
00041
        void setCommand(XPString_t *cmdNameOn, XPString_t *cmdNameOff);
00042
00045
       int getCommand();
00046
00048
       void processCommand();
00049
00054
        float value(float onValue, float offValue) { return on() ? onValue : offValue; };
00055
00056 private:
00057
        enum SwState_t
00058
00059
          switchOff,
00060
         switchOn
00061
00062
        uint8_t _mux;
00063
        uint8_t _pin;
00064
        uint8_t _debounce;
00065
        uint8_t _state;
       bool _transition;
int _cmdOff;
00066
00067
```

5.9 Timer.h 55

```
00068
        int _cmdOn;
00069 };
00070
00072 class Switch2
00073 {
00074 public:
00079
        Switch2(uint8_t mux, uint8_t pin1, uint8_t pin2);
08000
00084
        Switch2(uint8_t pin1, uint8_t pin2) : Switch2(NOT_USED, pin1, pin2) {}
00085
00087
        void handle();
00088
00090
        void handleXP() { handle(); processCommand(); };
00091
00094
        bool off()
                         { return _state == switchOff; };
00095
00098
        bool on1()
                         { return _state == switchOn1; };
00099
00102
        bool on2()
                         { return _state == switchOn2; };
00103
00107
        void setCommand(int cmdUp, int cmdDown);
00108
00112
        void setCommand(XPString_t *cmdNameUp, XPString_t *cmdNameDown);
00113
00118
        void setCommand(int cmdOn1, int cmdOff, int cmdOn2);
00119
00124
        void setCommand(XPString_t *cmdNameOn1, XPString_t *cmdNameOff, XPString_t *cmdNameOn2);
00125
00128
        int getCommand();
00129
00131
        void processCommand();
00132
00138
        float value(float on1Value, float offValue, float on2value) { return (on1() ? on1Value : on2() ?
      on2value : offValue); };
00139
00140 private:
        enum SwState_t
00141
00142
00143
          switchOff,
00144
          switchOn1,
00145
          switchOn2
00146
        }:
        uint8_t _mux;
00147
        uint8_t _pin1;
uint8_t _pin2;
uint8_t _lastState;
00148
00149
00150
        uint8_t _debounce;
uint8_t _state;
00151
00152
        bool _transition;
00153
00154
        int _cmdOff;
       int _cmdOn1;
int _cmdOn2;
00155
00156
00157 };
00158
00159 #endif
```

# 5.9 Timer.h

```
00001 #ifndef SoftTimer_h
00002 #define SoftTimer_h
00003 #include <Arduino.h>
00004
00006 class Timer
00007 {
80000
00011
          Timer(float cycle = 0); // ms
00012
00015
          void setCycle(float cycle);
00016
00019
          bool elapsed();
00020
00023
          float getTime(); // ms
00024
00027
          long count();
00028
        private:
00029
          unsigned long _cycleTime;
00030
          unsigned long _lastUpdateTime;
00031
          long _count;
00032 };
00033
00034 #endif
```

### 5.10 XPLDevices.h

```
00001 #ifndef XPLDevices_h
00002 #define XPLDevices_h
00003
00004 #include <XPLDirect.h>
00005 #include <Button.h>
00006 #include <Encoder.h>
00007 #include <Switch.h>
00008 #include <Cashift.h>
00008 #include <Timer.h>
00010 #include <DigitalIn.h>
00011 #include <AnalogIn.h>
00012
00013 #endif
```

# 5.11 XPLDirect.h

```
00001 /*
00002 XPLDirect.h - Library for serial interface to Xplane SDK.
        Created by Michael Gerlicher, September 2020.
       To report problems, download updates and examples, suggest enhancements or get technical support,
please visit my patreon page:
          www.patreon.com/curiosityworkshop
00006
        Stripped down to Minimal Version by mrusk, February 2023
00007 */
00008 #ifndef XPLDirect_h
00009 #define XPLDirect_h
00010 #include <Arduino.h>
00011
00012 #ifndef XPLDIRECT MAXDATAREFS ARDUINO
00013 #define XPLDIRECT_MAXDATAREFS_ARDUINO 100 // This can be changed to suit your needs and capabilities
      of your board.
00014 #endif
00015
00016 #ifndef XPLDIRECT_MAXCOMMANDS_ARDUINO
00017 #define XPLDIRECT MAXCOMMANDS ARDUINO 100 // Same here.
00018 #endif
00020 #define XPLDIRECT_RX_TIMEOUT 500 // after detecting a frame header, how long will we wait to receive
     the rest of the frame. (default 500)
00021
00022 #ifndef XPLMAX_PACKETSIZE
00023 #define XPLMAX_PACKETSIZE 80 // Probably leave this alone. If you need a few extra bytes of RAM it
      could be reduced, but it needs to
                                      // be as long as the longest dataref name + 10. If you are using
      datarefs
00025
                                      // that transfer strings it needs to be big enough for those too.
      (default 200)
00026 #endif
00027
00028 #ifndef XPL_USE_PROGMEM
00029 #define XPL_USE_PROGMEM 1
00030 #endif
00031
00033 // STOP! Dont change any other defines in this header!
00035
00036 #ifdef XPL USE PROGMEM
00037 // use Flash for strings, requires F() macro for strings in all registration calls
00038
        typedef const __FlashStringHelper XPString_t;
00039 #else
00040
       typedef const char XPString t;
00041 #endif
00042
00043 #define XPLDIRECT_BAUDRATE 115200 // don't mess with this, it needs to match the plugin which won't
00044 #define XPLDIRECT_PACKETHEADER '<' // ...or this
00045 #define XPLDIRECT_PACKETTRAILER '>' // ...or this
00046 #define XPLDIRECT_VERSION 2106171 // The plugin will start to verify that a compatible version is
      being used
00047 #define XPLDIRECT_ID 0
                                           // Used for relabled plugins to identify the company. 0 = normal
     distribution version
00048
00049 #define XPLERROR 'E'
                                                // %s
                                                               general error
00050 #define XPLRESPONSE_NAME '0'
00051 #define XPLRESPONSE_DATAREF '3'
                                                // %3.3i%s
                                                              dataref handle, dataref name
                                                              command handle, command name
00052 #define XPLRESPONSE_COMMAND '4'
                                                // %3.3i%s
00053 #define XPLRESPONSE_VERSION 'V'
00054 #define XPLCMD_PRINTDEBUG '1'
00055 #define XPLCMD_RESET '2'
00056 #define XPLCMD_SPEAK 'S'
00057 #define XPLCMD_SENDNAME 'a'
                                                // speak string
```

5.11 XPLDirect.h 57

```
00058 #define XPLREQUEST_REGISTERDATAREF 'b' // %1.11%2.21%5.51%s RWMode, array index (0 for non array
         datarefs), divider to decrease resolution, dataref name
                                                                      // just the name of the command to register
// nothing to request
00059 #define XPLREQUEST_REGISTERCOMMAND 'm'
00060 #define XPLREQUEST_NOREQUESTS 'c'
00061 #define XPLREQUEST_REFRESH 'd'
                                                                        \ensuremath{//} the plugin will call this once xplane is loaded in order to
         get fresh updates from arduino handles that write
00062 #define XPLCMD_DUMPREGISTRATIONS 'Z'
                                                                    // for debug purposes only (disabled)
00063 #define XPLCMD_DATAREFUPDATE 'e'
00064 #define XPLCMD_SENDREQUEST 'f'
00065 #define XPLCMD_DEVICEREADY 'g'
00066 #define XPLCMD_DEVICENOTREADY 'h'
00067 #define XPLCMD_COMMANDSTART 'i'
00068 #define XPLCMD_COMMANDEND 'j'
00069 #define XPLCMD_COMMANDTRIGGER 'k' // %3.3i%3.3i
                                                                                      command handle, number of triggers
00070 #define XPLCMD_SENDVERSION 'v' // we will respond with current build version
00071 #define XPL_EXITING 'x' // MG 03/14/2023: xplane sends this to the arduino device during
         normal shutdown of xplane. It may not happen if xplane crashes.
00072
00073 #define XPL_READ 1
00074 #define XPL_WRITE 2
00075 #define XPL_READWRITE 3
00076
00077 #define XPL_DATATYPE_INT 1
00078 #define XPL_DATATYPE_FLOAT 2
00079 #define XPL_DATATYPE_STRING 3
00081 class XPLDirect
00082 {
00083 public:
00084 XPLDirect(Stream*);
00085
            void begin(const char *devicename); // parameter is name of your device for reference
00086
            int connectionStatus(void);
           int commandTrigger(int commandHandle);
00087
                                                                                                        // triggers specified command 1 time;
           int commandTrigger(int commandHandle, int triggerCount); // triggers specified command triggerCount
88000
        times.
00089
           int commandStart(int commandHandle);
00090
            int commandEnd(int commandHandle);
            int datarefsUpdated();
                                                        // returns true if xplane has updated any datarefs since last call to
        datarefsUpdated()
00092
            int hasUpdated(int handle); // returns true if xplane has updated this dataref since last call to
         hasUpdated()
00093
           int registerDataRef(XPString_t *datarefName, int rwmode, unsigned int rate, float divider, long int
         *value);
00094
           int registerDataRef(XPString_t *datarefName, int rwmode, unsigned int rate, float divider, long int
*value, int index);
00095 int registerDataRef(XPString_t *datarefName, int rwmode, unsigned int rate, float divider, float
         *value);
{\tt 00096} \quad \text{int registerDataRef(XPString\_t *datarefName, int rwmode, unsigned int rate, float divider, float and the state of the s
        *value, int index);
00097 int registerDataRef(XPString_t *datarefName, int rwmode, unsigned int rate, char* value);
            int registerCommand(XPString_t *commandName);
            int sendDebugMessage(const char *msg);
00099
00100
            int sendSpeakMessage(const char* msg);
00101
            int allDataRefsRegistered(void);
00102
            void sendResetRequest(void);
00103
            int xloop(void); // where the magic happens!
00104 private:
00105
            void _processSerial();
            void _processPacket();
00106
00107
            void _sendPacketInt(int command, int handle, long int value); // for ints
            void _sendPacketFloat(int command, int handle, float value); // for floats
void _sendPacketVoid(int command, int handle); // just a command, int handle);
00108
                                                                                                              // just a command with a handle
00109
00110
            void _sendPacketString(int command, char *str);
                                                                                                              // for a string
00111
            void _transmitPacket();
            void _sendname();
00112
00113
            void _sendVersion();
00114
            int _getHandleFromFrame();
            int _getPayloadFromFrame(long int *);
00115
            int _getPayloadFromFrame(float *);
00116
00117
            int _getPayloadFromFrame(char *);
00118
00119
            Stream *streamPtr;
00120
            char *_deviceName;
            char _receiveBuffer[XPLMAX_PACKETSIZE];
00121
00122
            int receiveBufferBytesReceived;
            char _sendBuffer[XPLMAX_PACKETSIZE];
00123
00124
            int _connectionStatus;
00125
            int _dataRefsCount;
00126
            struct _dataRefStructure
00127
00128
               int dataRefHandle;
00129
               byte dataRefRWType;
                                                        // XPL_READ, XPL_WRITE, XPL_READWRITE
               byte dataRefVARType;
                                                        // XPL_DATATYPE_INT 1, XPL_DATATYPE_FLOAT 2 XPL_DATATYPE_STRING 3
00130
00131
               float divider;
                                                        // tell the host to reduce resolution by dividing then remultiplying by
        this number to reduce traffic. (ie .02, .1, 1, 5, 10, 100, 1000 etc) byte forceUpdate; // in case xplane plugin asks for a refresh
00132
00133
               unsigned long updateRate; // maximum update rate in milliseconds, 0 = every change
```

```
unsigned long lastUpdateTime;
00135
            XPString_t *dataRefName;
00136
            void *latestValue;
00137
           union {
            long int lastSentIntValue;
00138
              float lastSentFloatValue;
00139
00141
             \  \, \text{byte updatedFlag; // True if xplane has updated this dataref. Gets reset when we call has Updated } \\
         byte arrayIndex; // for datarefs that speak in arrays
} *_dataRefs[XPLDIRECT_MAXDATAREFS_ARDUINO];
00142
00143
00144
         int commandsCount;
         struct _commandStructure
00145
00146
00147
            int commandHandle;
00148
          XPString_t *commandName;
         } * commands[XPLDIRECT MAXCOMMANDS ARDUINO];
00149
00150 byte _allDataRefsRegistered; // becomes true if all datarefs have been registered

00151 byte _datarefsUpdatedFlag; // becomes true if any datarefs have been updated from xplane since
       last call to datarefsUpdated()
00152 };
00153
00155 extern XPLDirect XP;
00156
00157 #endif
```

# 5.12 Analogin.cpp

```
00001 #include <Arduino.h>
00002 #include "AnalogIn.h"
00003
00004 #define FULL_SCALE ((1 « AD_RES) - 1)
00005 #define HALF_SCALE (1 « (AD_RES - 1))
00006
00007 AnalogIn::AnalogIn(uint8_t pin, Analog_t type)
} 80000
       _pin = pin;
00009
        _filterConst = 1.0;
00010
00011
        _scale = 1.0;
00012
        pinMode(_pin, INPUT);
00013
         if (type == bipolar)
00014
         _offset = HALF_SCALE;
00015
         _scalePos = _scale / HALF_SCALE;
_scaleNeg = _scale / HALF_SCALE;
00016
00017
00018
00019
00020
00021
        _{offset} = 0;
          _scalePos = _scale / FULL_SCALE;
00022
          _scaleNeg = 0.0;
00023
00024
00025 }
00026
00027 AnalogIn::AnalogIn(uint8_t pin, Analog_t type, float timeConst) : AnalogIn(pin, type)
00028 {
        _filterConst = 1.0 / timeConst;
00029
00030 }
00031
00032 void AnalogIn::handle()
00033 {
00034
        int raw = raw();
00035
        _value = (_filterConst * _raw * (_raw >= 0 ? _scalePos : _scaleNeg)) + (1.0 - _filterConst) *
      _value;
00036 }
00037
00038 int AnalogIn::raw()
00039 {
        return analogRead(_pin) - _offset;
00040
00041 }
00043 void AnalogIn::calibrate()
00044 {
00045
        long sum = 0;
        for (int i = 0; i < 64; i++)</pre>
00046
00047
00048
          sum += analogRead(_pin);
00049
       _{\text{offset}} = (int)(sum / 64);
00050
       _____scalePos = (_offset < FULL_SCALE) ? _scale / (float)(FULL_SCALE - _offset) : 1.0;
_scaleNeg = (_offset > 0)? _scale / (float)(_offset) : 1.0;
00051
00052
00053 }
```

5.13 Button.cpp 59

# 5.13 Button.cpp

```
00001 #include <Arduino.h>
00002 #include <XPLDirect.h>
00003 #include "Button.h"
00004
00005 #ifndef DEBOUNCE_DELAY
00006 #define DEBOUNCE_DELAY 20
00007 #endif
80000
00009 // Buttons
00010 Button::Button(uint8_t mux, uint8_t pin)
00011 {
00012
        _{mux} = mux;
       _pin = pin;
_state = 0;
00013
00014
       _transition = 0;
00015
       _cmdPush = -1;
pinMode(_pin, INPUT_PULLUP);
00016
00017
00018 }
00019
00020 // use additional bit for input masking
00021 void Button::_handle(bool input)
00022 {
00023
        if (DigitalIn.getBit(_mux, _pin) && input)
00024
00025
          if (_state == 0)
00026
00027
            _state = DEBOUNCE_DELAY;
            _transition = transPressed;
00028
00029
00031
        else if (_state > 0)
00032
00033
          if (--_state == 0)
          _transition = transReleased;
}
00034
        {
00035
00036
00037
00038 }
00039
00040 void Button::setCommand(int cmdPush)
00041 {
        _cmdPush = cmdPush;
00042
00043 }
00044
00045 void Button::setCommand(XPString_t *cmdNamePush)
00046 {
        _cmdPush = XP.registerCommand(cmdNamePush);
00047
00048 }
00050 void Button::processCommand()
00051 {
00052
        if (pressed())
00053
       {
00054
          XP.commandStart ( cmdPush);
00055
00056
        if (released())
00057
00058
          XP.commandEnd(_cmdPush);
00059
00060 }
00061
00062 RepeatButton::RepeatButton(uint8_t mux, uint8_t pin, uint32_t delay) : Button(mux, pin)
00063 {
00064
        _delay = delay;
        _timer = 0;
00065
00066 }
00067
00068 void RepeatButton::_handle(bool input)
00069 {
00070
        if (DigitalIn.getBit(_mux, _pin) && input)
00071
00072
          if (_state == 0)
00073
            _state = DEBOUNCE_DELAY;
00075
            _transition = transPressed;
00076
            _timer = millis() + _delay;
00077
          else if (_delay > 0 && (millis() >= _timer))
00078
00079
08000
            _state = DEBOUNCE_DELAY;
00081
            _transition = transPressed;
00082
            _timer += _delay;
00083
          }
00084
00085
       else if (_state > 0)
```

# 5.14 DigitalIn.cpp

```
00001 #include <Arduino.h>
00002 #include "DigitalIn.h"
00003
00004 #define MCP_PIN 254
00005
00006 // constructor
00007 DigitalIn_::DigitalIn_()
00008 {
00009
         _numPins = 0;
        for (uint8_t expander = 0; expander < MUX_MAX_NUMBER; expander++)</pre>
00010
        _pin[expander] = NOT_USED;
00012
00013
        _s0 = NOT_USED;
00014
       _s1 = NOT_USED;
_s2 = NOT_USED;
00015
____ _ NOT_USED;

U0017    __s3 = NOT_USED;

00018 }
00016
00019
00020 // configure 74HC4067 adress pins S0-S3
00021 void DigitalIn_::setMux(uint8_t s0, uint8_t s1, uint8_t s2, uint8_t s3)
00022 {
00023
        _s1 = s1;
00024
        _s2 = s2;
_s3 = s3;
00025
00026
        pinMode(_s0, OUTPUT);
00027
00028
        pinMode(_s1, OUTPUT);
00029
        pinMode(_s2, OUTPUT);
00030
        pinMode(_s3, OUTPUT);
00031
        #ifdef ARDUINO_ARCH_AVR
00032
        _s0port = digitalPinToPort(_s0);
        _slport = digitalPinToPort(_s1);
00033
        _s2port = digitalPinToPort(_s2);
00034
        _s3port = digitalPinToPort(_s3);
00035
        _s0mask = digitalPinToBitMask(_s0);
00036
00037
        _slmask = digitalPinToBitMask(_sl);
        _s2mask = digitalPinToBitMask(_s2);
00038
00039
        _s3mask = digitalPinToBitMask(_s3);
00040
        #endif
00041 }
00042
00043 // Add a 74HC4067
00044 bool DigitalIn_::addMux(uint8_t pin)
00045 {
         if (_numPins >= MUX_MAX_NUMBER)
00046
00047
        {
00048
          return false;
00049
00050
        _pin[_numPins++] = pin;
00051
       pinMode(pin, INPUT);
00052
        return true:
00053 }
00055 #if MCP_MAX_NUMBER > 0
00056 // Add a MCP23017
00057 bool DigitalIn_::addMCP(uint8_t adress)
00058 {
00059
        if (_numMCP >= MCP_MAX_NUMBER)
00060
        {
          return false;
00062
00063
         if (!_mcp[_numMCP].begin_I2C(adress, &Wire))
00064
00065
          return false:
00066
00067
         for (int i = 0; i < 16; i++)
00068
          // TODO: register write iodir = 0xffff, ipol = 0xffff, gppu = 0xffff
_mcp[_numMCP].pinMode(i, INPUT_PULLUP);
00069
00070
00071
        _numMCP++;
00072
        _pin[_numPins++] = MCP_PIN;
```

5.15 Encoder.cpp 61

```
return true;
00075 }
00076 #endif
00077
00078 // Gets specific channel from expander, number according to initialization order
00079 bool DigitalIn_::getBit(uint8_t expander, uint8_t channel)
00081
00082
00083
       #ifdef ARDUINO ARCH AVR
         return (*portInputRegister(digitalPinToPort(channel)) & digitalPinToBitMask(channel)) ? false :
00084
     true:
00085
       #else
00086
          return !digitalRead(channel);
00087
        #endif
00088
00089
        return bitRead(_data[expander], channel);
00090 }
00092 // read all inputs together -> base for board specific optimization by using byte read
00093 void DigitalIn_::handle()
00094 {
00095
        // only if Mux Pins present
00096 #if MCP_MAX_NUMBER > 0
00097
        if (_numPins > _numMCP)
00098 #else
00099
       if (_numPins > 0)
00100 #endif
00101
       {
00102
          for (uint8_t channel = 0; channel < 16; channel++)</pre>
00103
00104 #ifdef ARDUINO_ARCH_AVR
00105
          uint8_t oldSREG = SREG;
00106
            cli();
00107
            bitRead(channel, 0) ? *portOutputRegister(_s0port) |= _s0mask : *portOutputRegister(_s0port) &=
     ~_s0mask;
00108
           bitRead(channel, 1) ? *portOutputRegister(_slport) |= _slmask : *portOutputRegister(_slport) &=
      ~_slmask;
00109
           bitRead(channel, 2) ? *portOutputRegister(_s2port) |= _s2mask : *portOutputRegister(_s2port) &=
00110
           bitRead(channel, 3) ? *portOutputRegister(_s3port) |= _s3mask : *portOutputRegister(_s3port) &=
     ~_s3mask;
00111
           SREG = oldSREG:
00112
           delayMicroseconds(1);
00113 #else
00114
           digitalWrite(_s0, bitRead(channel, 0));
00115
            digitalWrite(_s1, bitRead(channel, 1));
00116
            digitalWrite(\_s2, bitRead(channel, 2));
00117
           digitalWrite(_s3, bitRead(channel, 3));
00118 #endif
            for (uint8_t expander = 0; expander < _numPins; expander++)</pre>
00120
00121
              if (_pin[expander] != MCP_PIN)
00122
00123 #ifdef ARDUINO_ARCH_AVR
00124
               bitWrite(_data[expander], channel, (*portInputRegister(digitalPinToPort(_pin[expander])) &
     digitalPinToBitMask(_pin[expander])) ? false : true);
00125 #else
00126
                bitWrite(_data[expander], channel, !digitalRead(_pin[expander]));
00127 #endif
00128
             }
00129
           }
00130
         }
00131
00132 #if MCP_MAX_NUMBER > 0
00133 int mcp = 0;
        for (uint8_t expander = 0; expander < _numPins; expander++)</pre>
00134
00135
        if (_pin[expander] == MCP_PIN)
00136
        {
00138
            _data[expander] = ~_mcp[mcp++].readGPIOAB();
00139
00140
       }
00141 #endif
00142 }
00144 DigitalIn_ DigitalIn;
```

# 5.15 Encoder.cpp

```
00001 #include <Arduino.h>
00002 #include <XPLDirect.h>
00003 #include "Encoder.h"
```

```
00004
00005 #ifndef DEBOUNCE_DELAY
00006 #define DEBOUNCE_DELAY 20
00007 #endif
80000
00009 // Encoder with button functionality on MUX
00010 Encoder::Encoder(uint8_t mux, uint8_t pin1, uint8_t pin2, uint8_t pin3, EncPulse_t pulses)
00011 {
00012
        _pin1 = pin1;
_pin2 = pin2;
00013
00014
        _pin3 = pin3;
_pulses = pulses;
_count = 0;
00015
00016
00017
00018
        _state = 0;
        _transition = transNone;
00019
00020
        \_cmdUp = -1;
        _cmdDown = -1;
_cmdPush = -1;
00021
00022
        pinMode(_pin1, INPUT_PULLUP);
pinMode(_pin2, INPUT_PULLUP);
00023
00024
00025
         if (_pin3 != NOT_USED)
00026
          pinMode(_pin3, INPUT_PULLUP);
00027
00028
        }
00029 }
00030
00031 // real time handling
00032 void Encoder::handle()
00033 {
00034
        // collect new state
00035
         _state = ((_state & 0x03) « 2) | (DigitalIn.getBit(_mux, _pin2) « 1) | (DigitalIn.getBit(_mux,
      _pin1));
        // evaluate state change
00036
00037
        if (_state == 1 || _state == 7 || _state == 8 || _state == 14)
00038
00039
          _count++;
00040
00041
         if (_state == 2 || _state == 4 || _state == 11 || _state == 13)
00042
          _count--;
00043
00044
        if (_state == 3 || _state == 12)
00045
00046
          _count += 2;
00047
00048
00049
        if (_state == 6 || _state == 9)
00050
00051
          _count -= 2;
00052
00053
00054
         // optional button functionality
00055
         if (_pin3 != NOT_USED)
00056
00057
          if (DigitalIn.getBit(_mux, _pin3))
00058
00059
             if (_debounce == 0)
00060
             {
00061
              _debounce = DEBOUNCE_DELAY;
00062
              _transition = transPressed;
00063
00064
00065
          else if (_debounce > 0)
00066
00067
             if (--_debounce == 0)
00068
           {
              _transition = transReleased;
00069
00070
00071
          }
00072
        }
00073 }
00074
00075 void Encoder::setCommand(int cmdUp, int cmdDown, int cmdPush)
00076 {
00077
        _cmdUp = cmdUp;
00078
        _cmdDown = cmdDown;
00079
        _cmdPush = cmdPush;
00080 }
00081
00082 void Encoder::setCommand(XPString t *cmdNameUp, XPString t *cmdNameDown, XPString t *cmdNamePush)
00083 {
00084
        _cmdUp = XP.registerCommand(cmdNameUp);
        _cmdDown = XP.registerCommand(cmdNameDown);
_cmdPush = XP.registerCommand(cmdNamePush);
00085
00086
00087 }
00088
00089 void Encoder::setCommand(int cmdUp, int cmdDown)
```

5.16 LedShift.cpp 63

```
00090 {
00091
       _cmdUp = cmdUp;
00092
       _cmdDown = cmdDown;
       \_cmdPush = -1;
00093
00094 }
00095
00096 void Encoder::setCommand(XPString_t *cmdNameUp, XPString_t *cmdNameDown)
00097 {
00098
       _cmdUp = XP.registerCommand(cmdNameUp);
       00099
00100
00101 }
00102
00103 int Encoder::getCommand(EncCmd_t cmd)
00104 {
00105
       switch (cmd)
00106
00107
       case encCmdUp:
        return _cmdUp;
00108
00109
         break;
00110
       case encCmdDown:
       return _cmdDown;
break;
00111
00112
       case encCmdPush:
00113
00114
       return _cmdPush;
break;
00115
00116
       default:
        return -1;
00117
00118
         break;
00119
       }
00120 }
00121
00122 void Encoder::processCommand()
00123 {
00124
        if (up())
00125
00126
         XP.commandTrigger(_cmdUp);
00128
       if (down())
00129
00130
         XP.commandTrigger(_cmdDown);
00131
       if (_cmdPush >= 0)
00132
00133
00134
          if (pressed())
00135
00136
           XP.commandStart(_cmdPush);
00137
00138
          if (released())
00139
00140
           XP.commandEnd(_cmdPush);
00141
00142
00143 }
```

# 5.16 LedShift.cpp

```
00001 #include <Arduino.h>
00002 #include "LedShift.h"
00003
00004 #define BLINK_DELAY 150
00005
00006 LedShift::LedShift(uint8_t pin_DAI, uint8_t pin_DCK, uint8_t pin_LAT)
80000
         _pin_DAI = pin_DAI;
        _pin_DCK = pin_DCK;
00009
        _pin_LAT = pin_LAT;
00010
        _count = 0;
_state = 0;
00011
00012
         _timer = millis() + BLINK_DELAY;
for (int pin = 0; pin < 16; pin++)
00013
00014
00015
           _mode[pin] = ledOff;
00016
00017
00018
        pinMode (_pin_DAI, OUTPUT);
00019
         pinMode(_pin_DCK, OUTPUT);
00020
         pinMode(_pin_LAT, OUTPUT);
00021
         digitalWrite(_pin_DAI, LOW);
00022
         digitalWrite(_pin_DCK, LOW);
00023
         digitalWrite(_pin_LAT, LOW);
00024
         _send();
00025 }
00026
```

```
00027 // send 16 bit
00028 void LedShift::_send()
00029 {
00030
        // get bit masks
        uint8_t dataPort = digitalPinToPort(_pin_DAI);
uint8_t dataMask = digitalPinToBitMask(_pin_DAI);
00031
00032
        uint8_t clockPort = digitalPinToPort(_pin_DCK);
00034
        uint8_t clockMask = digitalPinToBitMask(_pin_DCK);
        uint16_t val = _state;
for (uint8_t i = 16; i > 0; --i)
00035
00036
00037
          (val & 0x8000) > 0 ? *portOutputRegister(dataPort) |= dataMask : *portOutputRegister(dataPort) &=
00038
      ~dataMask;
00039
        *portOutputRegister(clockPort) |= clockMask;
00040
           *portOutputRegister(clockPort) &= ~clockMask;
00041
          val «= 1;
00042
00043
        // latch LAT signal
        clockPort = digitalPinToPort(_pin_LAT);
00045
        clockMask = digitalPinToBitMask(_pin_LAT);
00046
        *portOutputRegister(clockPort) |= clockMask;
        *portOutputRegister(clockPort) &= ~clockMask;
00047
00048 }
00049
00050 void LedShift::_set(uint8_t pin)
00051 {
00052
        switch (_mode[pin])
00053
00054
        case ledOn:
         bitSet(_state, pin);
00055
00056
          break;
00057
        case ledFast:
00058
        bitWrite(_state, pin, bitRead(_count, 0));
00059
          break;
00060
        case ledMedium:
00061
        bitWrite(_state, pin, bitRead(_count, 1));
00062
          break;
        case ledSlow:
00063
        bitWrite(_state, pin, bitRead(_count, 2));
00064
00065
          break;
00066
        default:
00067
         bitClear(_state, pin);
00068
00069 }
00070
00071 void LedShift::set(uint8_t pin, led_t mode)
00072 {
        _mode[pin] = mode;
00073
00074
        _set(pin);
00075
        _update = true;
00077
00078 void LedShift::setAll(led_t mode)
00079 {
        for (int pin = 0; pin < 16; pin++)</pre>
08000
00081
         _mode[pin] = mode;
       __set(pin);
00083
00084
u0085    _update = true;
00086 }
00087
00088 void LedShift::handle()
00089 {
00090
        if (millis() >= _timer)
00091
          _timer += BLINK_DELAY;
00092
          _count = (_count + 1) % 8;
for (int pin = 0; pin < 16; pin++)
00093
00094
00095
00096
            _set(pin);
00097
          _update = true;
00098
00099
00100
        if (update)
00101
00102
          _send();
00103
          _update = false;
00104
00105 }
```

# 5.17 Switch.cpp

00001 #include <Arduino.h>

5.17 Switch.cpp 65

```
00002 #include <XPLDirect.h>
00003 #include "Switch.h"
00004
00005 #ifndef DEBOUNCE DELAY
00006 #define DEBOUNCE DELAY 20
00007 #endif
00009 Switch::Switch(uint8_t mux, uint8_t pin)
00010 {
00011
       _{mux} = mux;
       _pin = pin;
00012
       _state = switchOff;
_cmdOff = -1;
00013
00014
        \_cmdOn = -1;
00015
00016
       pinMode(_pin, INPUT_PULLUP);
00017 }
00018
00019 void Switch::handle()
00020 {
00021
        if (_debounce > 0)
00022
         _debounce--;
00023
00024
       else
00025
00026
00027
        SwState_t input = switchOff;
00028
          if (DigitalIn.getBit(_mux, _pin))
00029
00030
           input = switchOn;
00031
00032
          if (input != _state)
00033
         {
00034
           _debounce = DEBOUNCE_DELAY;
00035
           _state = input;
           _transition = true;
00036
         }
00037
00038
       }
00040
00041 void Switch::setCommand(int cmdOn, int cmdOff)
00042 {
       _cmdOn = cmdOn;
00043
        _cmdOff = cmdOff;
00044
00045 }
00047 void Switch::setCommand(XPString_t *cmdNameOn, XPString_t *cmdNameOff)
00048 {
00049
       _cmdOn = XP.registerCommand(cmdNameOn);
       _cmdOff = XP.registerCommand(cmdNameOff);
00050
00051 }
00052
00053 int Switch::getCommand()
00054 {
00055
        switch (_state)
00056
00057
       case switchOff:
       return _cmdOff;
break;
00059
00060
       case switchOn:
        return _cmdOn;
break;
00061
00062
00063
       default:
        return -1;
break;
00064
00065
00066
00067 }
00068
00069 void Switch::processCommand()
00070 {
        if (_transition)
00072
       {
00073
         XP.commandTrigger(getCommand());
       _transition = false;
}
00074
00075
00076 }
00077
00078 // Switch 2
00079
00080 Switch2::Switch2(uint8_t mux, uint8_t pin1, uint8_t pin2)
00081 {
       _mux = mux;
00082
        _pin1 = pin1;
00083
       _pin2 = pin2;
00084
       _state = switchOff;
00085
       _cmdOff = -1;
_cmdOn1 = -1;
00086
00087
        \_cmdOn2 = -1;
00088
```

```
if (_mux == NOT_USED)
00090
       {
00091
         pinMode(_pin1, INPUT_PULLUP);
00092
         pinMode(_pin2, INPUT_PULLUP);
00093
00094 }
00095
00096 void Switch2::handle()
00097 {
00098
        if (_debounce > 0)
00099
       {
         _debounce--;
00100
00101
00102
00103
00104
         SwState_t input = switchOff;
00105
          if (DigitalIn.getBit(_mux, _pin1))
00106
00107
           input = switchOn1;
00108
00109
          else if (DigitalIn.getBit(_mux, _pin2))
00110
00111
           input = switchOn2;
00112
00113
          if (input != _state)
00114
           _debounce = DEBOUNCE_DELAY;
00115
00116
           _lastState = _state;
00117
           _state = input;
           _transition = true;
00118
00119
00120
       }
00121 }
00122
00123 void Switch2::setCommand(int cmdUp, int cmdDown)
00124 {
       _cmdOn1 = cmdUp;
00125
       _cmdOff = cmdDown;
       \_cmdOn2 = -1;
00127
00128 }
00129
00130 void Switch2::setCommand(XPString_t *cmdNameUp, XPString_t *cmdNameDown)
00131 {
       _cmdOn1 = XP.registerCommand(cmdNameUp);
00132
       _cmdOff = XP.registerCommand(cmdNameDown);
00133
       \_cmdOn2 = -1;
00134
00135 }
00136
00137 void Switch2::setCommand(int cmdOn1, int cmdOff, int cmdOn2)
00138 {
00139
       _cmdOn1 = cmdOn1;
00140
       _cmdOff = cmdOff;
       \_cmdOn2 = cmdOn2;
00141
00142 }
00143
00144 void Switch2::setCommand(XPString_t *cmdNameOn1, XPString_t *cmdNameOff, XPString_t *cmdNameOn2)
00145 {
00146
       _cmdOn1 = XP.registerCommand(cmdNameOn1);
00147
       _cmdOff = XP.registerCommand(cmdNameOff);
       _cmdOn2 = XP.registerCommand(cmdNameOn2);
00148
00149 }
00150
00151 int Switch2::getCommand()
00152 {
00153
        if (_cmdOn2 == -1)
00154
         if (_state == switchOn1)
00155
00156
          {
00157
           return cmdOn1:
00158
00159
          if (_state == switchOff && _lastState == switchOn1)
00160
          {
00161
           return _cmdOff;
00162
00163
          if ( state == switchOn2)
00164
           return _cmdOff;
00165
00166
          if (_state == switchOff && _lastState == switchOn2)
00167
00168
         {
00169
           return _cmdOn1;
00170
          }
00171
00172
        else
00173
          if (_state == switchOn1)
00174
00175
```

5.18 Timer.cpp 67

```
return _cmdOn1;
00177
00178
          if (_state == switchOff)
00179
00180
           return _cmdOff;
00181
00182
         if (_state == switchOn2)
00183
         {
00184
           return _cmdOn2;
00185
         }
       }
00186
00187
       return -1;
00188 }
00189
00190 void Switch2::processCommand()
00191 {
        if (_transition)
00192
00193
        XP.commandTrigger(getCommand());
00195
         _transition = false;
00196 }
00197 }
```

## 5.18 Timer.cpp

```
00001 #include <Arduino.h>
00002 #include "Timer.h"
00003
00004 Timer::Timer(float cycle)
00005 {
00009
00010 void Timer::setCycle(float cycle)
00011 {
       _cycleTime = (unsigned long)(cycle * 1000.0);
00012
00013 }
00014
00015 bool Timer::elapsed()
00016 {
       _count++;
00017
       unsigned long now = micros();
00018
       if (now > _lastUpdateTime + _cycleTime)
00019
00020
       _lastUpdateTime = now;
return true;
00021
00022
00023
00024
       return false;
00025 }
00026
00027 float Timer::getTime()
00028 {
00029
       unsigned long now = micros();
00030
       unsigned long cycle = now - _lastUpdateTime;
       _lastUpdateTime = now;
00031
       return (float)cycle * 0.001;
00032
00033 }
00034
00035 long Timer::count()
00036 {
00037
       long ret = _count;
       _count = 0;
00038
       return ret;
00040 }
```

```
00001 /*
00002 XPLDirect.cpp
00003 Created by Michael Gerlicher, September 2020.
00004 Modified by mrusk, March 2023
00005 */
00006
00007 #include <Arduino.h>
00008 #include "XPLDirect.h"
00009
00010 // Methods
00011 XPLDirect::XPLDirect(Stream* device)
```

```
00012 {
00013
        streamPtr = device;
00014
        streamPtr->setTimeout(XPLDIRECT_RX_TIMEOUT);
00015 }
00016
00017 void XPLDirect::begin(const char *devicename)
00018 {
00019
        _deviceName = (char *)devicename;
        _connectionStatus = 0;
00020
        _dataRefsCount = 0;
00021
        _commandsCount = 0;
00022
        _allDataRefsRegistered = 0;
00023
        _receiveBuffer[0] = 0;
00024
00025 }
00026
00027 int XPLDirect::xloop(void)
00028 {
        _processSerial();
00029
00030
        if (!_allDataRefsRegistered)
00031
00032
          return connectionStatus;
00033
        \ensuremath{//} process datarefs to send
00034
        for (int i = 0; i < _dataRefsCount; i++)</pre>
00035
00036
        {
          if (_dataRefs[i]->dataRefHandle >= 0 && (_dataRefs[i]->dataRefRWType == XPL_WRITE ||
00037
      _dataRefs[i]->dataRefRWType == XPL_READWRITE))
00038
00039
            if ((millis() - _dataRefs[i]->lastUpdateTime > _dataRefs[i]->updateRate) ||
      _dataRefs[i]->forceUpdate)
00040
            {
00041
              switch (_dataRefs[i]->dataRefVARType)
00042
00043
              case XPL_DATATYPE_INT:
00044
                if (*(long int *)_dataRefs[i]->latestValue != _dataRefs[i]->lastSentIntValue)
00045
                {
                   _sendPacketInt(XPLCMD_DATAREFUPDATE, _dataRefs[i]->dataRefHandle, *(long int
00046
     *)_dataRefs[i]->latestValue);
00047
                 _dataRefs[i]->lastSentIntValue = *(long int *)_dataRefs[i]->latestValue;
00048
                  _dataRefs[i]->lastUpdateTime = millis();
                  _dataRefs[i]->forceUpdate = 0;
00049
                }
00050
00051
                break:
00052
              case XPL_DATATYPE_FLOAT:
00053
                if (_dataRefs[i]->divider > 0)
00054
                {
_dataRefs[i]->divider) * _dataRefs[i]->divider);
00056
00055
                  *(float *)_dataRefs[i]->latestValue = ((int)(*(float *)_dataRefs[i]->latestValue /
00057
                 if (*(float *) dataRefs[i]->latestValue != dataRefs[i]->lastSentFloatValue)
00058
                {
                   _sendPacketFloat(XPLCMD_DATAREFUPDATE, _dataRefs[i]->dataRefHandle, *(float
     *)_dataRefs[i]->latestValue);
                 _dataRefs[i]->lastSentFloatValue = *(float *)_dataRefs[i]->latestValue;
_dataRefs[i]->lastUpdateTime = millis();
00060
00061
                  _dataRefs[i]->forceUpdate = 0;
00062
00063
00064
                break;
00065
00066
            }
00067
         }
00068
00069
        return _connectionStatus;
00070 }
00071
00072 int XPLDirect::commandTrigger(int commandHandle)
00073 {
00074
        if (commandHandle < 0 || commandHandle >= commandsCount)
00075
        { // invalid handle
00076
          return -1;
00077
        if (!_commands[commandHandle])
00078
        { // inactive command
00079
00080
          return -1:
00081
00082 #if XPL_DEBUG
00083
        Serial.print("Command Trigger: ");
00084
        Serial.println(_commands[commandHandle]->commandName);
00085 #endif
        _sendPacketInt(XPLCMD_COMMANDTRIGGER, _commands[commandHandle]->commandHandle, 1);
00086
00087
        return 0;
00088 }
00089
00090 int XPLDirect::commandTrigger(int commandHandle, int triggerCount)
00091 {
        if (commandHandle < 0 || commandHandle >= _commandsCount)
00092
00093
        { // invalid handle
```

```
00094
          return -1;
00095
00096
        if (!_commands[commandHandle])
        { // inactive command
00097
00098
          return -1;
00099
00100 #if XPL_DEBUG
00101
        Serial.print("Command Trigger: ");
        Serial.print(_commands[commandHandle]->commandName);
Serial.print(" ");
00102
00103
        Serial.print(triggerCount);
Serial.println(" times");
00104
00105
00106 #endif
        _sendPacketInt(XPLCMD_COMMANDTRIGGER, _commands[commandHandle] -> commandHandle, (long
     int)triggerCount);
00108
       return 0;
00109 }
00110
00111 int XPLDirect::commandStart(int commandHandle)
00112 {
00113
        if (commandHandle < 0 || commandHandle >= _commandsCount)
00114
        \{\ //\ {\hbox{invalid handle}}
          return -1;
00115
00116
00117
        if (!_commands[commandHandle])
00118
        { // inactive command
00119
          return -1;
00120
00121 #if XPL_DEBUG
        Serial.print("Command Start : ");
00122
00123
        Serial.println(_commands[commandHandle]->commandName);
00124 #endif
00125
       _sendPacketVoid(XPLCMD_COMMANDSTART, _commands[commandHandle]->commandHandle);
00126
        return 0;
00127 }
00128
00129 int XPLDirect::commandEnd(int commandHandle)
00130 {
00131
        if (commandHandle < 0 || commandHandle >= _commandsCount)
00132
        { // invalid handle
00133
          return -1;
00134
        if (!_commands[commandHandle])
00135
       { // inactive command
00136
00137
         return -1;
00138
00139 #if XPL DEBUG
00140 Serial.print("Command End
                                     : ");
       Serial.println(_commands[commandHandle]->commandName);
00141
00142 #endif
00143
        _sendPacketVoid(XPLCMD_COMMANDEND, _commands[commandHandle]->commandHandle);
00144
00145 }
00146
00147 int XPLDirect::connectionStatus()
00148 {
        return _connectionStatus;
00150 }
00151
00152 int XPLDirect::sendDebugMessage(const char* msg)
00153 {
         _sendPacketString(XPLCMD_PRINTDEBUG, (char *)msg);
00154
00155
        return 1;
00156 }
00157
00158 int XPLDirect::sendSpeakMessage(const char* msg)
00159 {
        _sendPacketString(XPLCMD_SPEAK, (char *)msg);
00160
00161
        return 1:
00162 }
00163
00164 int XPLDirect::hasUpdated(int handle)
00165 {
        if (_dataRefs[handle]->updatedFlag)
00166
00167
       {
00168
         _dataRefs[handle]->updatedFlag = false;
00169
          return true;
00170
00171
        return false;
00172 }
00173
00174 int XPLDirect::datarefsUpdated()
00175 {
00176
        if (_datarefsUpdatedFlag)
00177
        {
00178
          _datarefsUpdatedFlag = false;
00179
          return true;
```

```
00180
00181
        return false;
00182 }
00183
00184 void XPLDirect::_sendname()
00185 {
00186
        if (_deviceName != NULL)
00187
00188
         _sendPacketString(XPLRESPONSE_NAME, _deviceName);
00189
       }
00190 }
00191
00192 void XPLDirect::_sendVersion()
00193 {
00194
        if (_deviceName != NULL)
       _sendPacketInt(XPLRESPONSE_VERSION, XPLDIRECT_ID, XPLDIRECT_VERSION);
}
00195
00196
00197
00198 }
00199
00200 void XPLDirect::sendResetRequest()
00201 {
00202
        if (_deviceName != NULL)
00203
          _sendPacketVoid(XPLCMD_RESET, 0);
00204
00205 }
00206 }
00207
00208 void XPLDirect::_processSerial()
00209 {
00210
       while (streamPtr->available() && _receiveBuffer[0] != XPLDIRECT_PACKETHEADER)
00211
00212
          _receiveBuffer[0] = (char)streamPtr->read();
00213
00214
        if (_receiveBuffer[0] != XPLDIRECT_PACKETHEADER)
00215
00216
          return;
00217
00218
        _receiveBufferBytesReceived = streamPtr->readBytesUntil(XPLDIRECT_PACKETTRAILER, (char
      *)&_receiveBuffer[1], XPLMAX_PACKETSIZE - 1);
00219
           (_receiveBufferBytesReceived == 0)
00220
       {
          _receiveBuffer[0] = 0;
00221
00222
          return;
00223
       _receiveBuffer[++_receiveBufferBytesReceived] = XPLDIRECT_PACKETTRAILER;
00224
00225
       _receiveBuffer[++_receiveBufferBytesReceived] = 0; // old habits die hard.
       _processPacket();
00226
       _receiveBuffer[0] = 0;
00227
00228 }
00229
00230 void XPLDirect::_processPacket()
00231 {
00232
        int i:
00233
00234
        switch (_receiveBuffer[1])
00235
       case XPLCMD_RESET:
00236
        _connectionStatus = false;
break;
00237
00238
00239
        case XPL EXITING :
                                  // MG 03/14/2023: Added protocol code so the device will know if xplane
00240
     has shut down normally.
00241
          _connectionStatus = false;
00242
00243
        case XPLCMD_SENDNAME:
00244
         _sendname();
00245
00246
          _connectionStatus = true;
                                               // not considered active till you know my name
          for (i = 0; i < _dataRefsCount; i++) // also, if name was requested reset active datarefs and
00247
      commands
00248
           _dataRefs[i]->dataRefHandle = -1; // invalid again until assigned by Xplane
00249
00250
00251
          for (i = 0; i < commandsCount; i++)</pre>
00252
            _commands[i]->commandHandle = -1;
00253
00254
00255
          break:
00256
00257
        case XPLCMD SENDVERSION:
00258
00259
           sendVersion();
00260
00261
00262
00263
        case XPLRESPONSE_DATAREF:
```

```
00264
          for (int i = 0; i < _dataRefsCount; i++)</pre>
00265
           if (strncmp_PF((char *)&_receiveBuffer[5], (uint_farptr_t)_dataRefs[i]->dataRefName,
00266
     strlen_PF((uint_farptr_t)_dataRefs[i]->dataRefName)) == 0 && _dataRefs[i]->dataRefHandle == -1)
00267
00268
              _dataRefs[i]->dataRefHandle = _getHandleFromFrame(); // parse the refhandle
              _dataRefs[i]->updatedFlag = true;
00270
              i = _dataRefsCount; // end checking
00271
00272
00273
         break:
00274
00275
        case XPLRESPONSE_COMMAND:
00276
         for (int i = 0; i < _commandsCount; i++)</pre>
00277
            if (strncmp_PF((char *)&_receiveBuffer[5], (uint_farptr_t)_commands[i]->commandName,
00278
     strlen_PF((uint_farptr_t)_commands[i]->commandName)) == 0 && _commands[i]->commandHandle == -1)
00279
00280
              _commands[i]->commandHandle = _getHandleFromFrame(); // parse the refhandle
00281
              i = _commandsCount;
                                                                     // end checking
00282
00283
00284
         break;
00285
00286
        case XPLCMD_SENDREQUEST:
00288
          int packetSent = 0;
00289
         int i = 0;
00290
          while (!packetSent && i < _dataRefsCount && i < XPLDIRECT_MAXDATAREFS_ARDUINO) // send dataref</pre>
     registrations first
00291
         {
00292
            if (_dataRefs[i]->dataRefHandle =
                                                -1)
00293
            \{\ //\  \, \text{some boards cant do sprintf with floats so this is a workaround}\ \,
00294
             sprintf(_sendBuffer, "%c%c%1.1i%2.2i%05i.%02i%S%c", XPLDIRECT_PACKETHEADER,
     XPLREQUEST_REGISTERDATAREF, _dataRefs[i]->dataRefrWType, _dataRefs[i]->arrayIndex,
00295
                      (int)_dataRefs[i]->divider, (int)(_dataRefs[i]->divider * 100) % 100, (wchar_t
      *)_dataRefs[i]->dataRefName, XPLDIRECT_PACKETTRAILER);
00296
              _transmitPacket();
00297
              packetSent = 1;
00298
00299
            i++;
00300
         i = 0;
00301
          while (!packetSent && i < _commandsCount && i < XPLDIRECT_MAXCOMMANDS_ARDUINO) // now send command</pre>
00302
     registrations
00303
         {
00304
            if (_commands[i]->commandHandle == -1)
00305
            {
              sprintf(_sendBuffer, "%c%c%%%c", XPLDIRECT_PACKETHEADER, XPLREQUEST_REGISTERCOMMAND, (wchar_t
00306
     *)_commands[i]->commandName, XPLDIRECT_PACKETTRAILER);
00307
              _transmitPacket();
00308
              packetSent = 1;
00309
00310
           i++;
00311
00312
          if (!packetSent)
00314
            _allDataRefsRegistered = true;
            sprintf(_sendBuffer, "%c%c%c", XPLDIRECT_PACKETHEADER, XPLREQUEST_NOREQUESTS,
     XPLDIRECT_PACKETTRAILER);
           _transmitPacket();
00316
00317
00318
         break;
00319
00320
00321
        case XPLCMD_DATAREFUPDATE:
00322
          int refhandle = _getHandleFromFrame();
00323
          for (int i = 0; i < _dataRefsCount; i++)</pre>
00324
         {
            if (_dataRefs[i]->dataRefHandle == refhandle && (_dataRefs[i]->dataRefRWType == XPL_READ ||
00326
      _dataRefs[i]->dataRefRWType == XPL_READWRITE))
00327
              if (_dataRefs[i]->dataRefVARType == XPL_DATATYPE_INT)
00328
00329
              {
                _getPayloadFromFrame((long int *)_dataRefs[i]->latestValue);
00330
00331
                _dataRefs[i]->lastSentIntValue = *(long int *)_dataRefs[i]->latestValue;
00332
                _dataRefs[i]->updatedFlag = true;
00333
                _datarefsUpdatedFlag = true;
00334
00335
              if ( dataRefs[i]->dataRefVARType == XPL DATATYPE FLOAT)
00336
              {
                _getPayloadFromFrame((float *)_dataRefs[i]->latestValue);
00337
00338
                _dataRefs[i]->lastSentFloatValue = *(float *)_dataRefs[i]->latestValue;
00339
                _dataRefs[i]->updatedFlag = true;
                _datarefsUpdatedFlag = true;
00340
00341
```

```
if (_dataRefs[i]->dataRefVARType == XPL_DATATYPE_STRING)
00343
                                     _getPayloadFromFrame((char *)_dataRefs[i]->latestValue);
_dataRefs[i]->updatedFlag = true;
00344
00345
00346
                                       _datarefsUpdatedFlag = true;
00347
00348
                                 i = _dataRefsCount; // skip the rest
00349
                             }
00350
00351
                       break;
                   }
00352
00353
                   case XPLREOUEST REFRESH:
                        for (int i = 0; i < _dataRefsCount; i++)</pre>
00354
00355
00356
                             if (_dataRefs[i]->dataRefRWType == XPL_WRITE || _dataRefs[i]->dataRefRWType == XPL_READWRITE)
00357
                                    _dataRefs[i]->forceUpdate = 1; // bypass noise and timing filters
00358
00359
                            }
00360
00361
                       break;
00362
00363
                   default:
00364
                      break;
00365
00366 }
00367
00368 void XPLDirect::_sendPacketInt(int command, int handle, long int value) // for ints
00369 {
00370
                   if (handle >= 0)
00371
                   {
                       sprintf(_sendBuffer, "%c%c%3.3i%ld%c", XPLDIRECT_PACKETHEADER, command, handle, value,
00372
             XPLDIRECT_PACKETTRAILER);
00373
                       _transmitPacket();
00374
00375 }
00376
00377 void XPLDirect::_sendPacketFloat(int command, int handle, float value) // for floats
00378 {
00379
                    if (handle >= 0)
00380
00381
                       \ensuremath{//} some boards cant do sprintf with floats so this is a workaround.
00382
                        char tmp[16];
                       dtostrf(value, 8, 6, tmp); sprintf(_sendBuffer, "%c%c%3.3i%s%c", XPLDIRECT_PACKETHEADER, command, handle, tmp,
00383
00384
             XPLDIRECT_PACKETTRAILER);
                       _transmitPacket();
00385
00386
00387 }
00388
00389 void XPLDirect::_sendPacketVoid(int command, int handle) // just a command with a handle
00390 {
00391
00392
                   {
00393
                        sprintf(_sendBuffer, "%c%c%3.3i%c", XPLDIRECT_PACKETHEADER, command, handle,
             XPLDIRECT PACKETTRAILER);
00394
                       _transmitPacket();
00395
00396 }
00397
00398 void XPLDirect::_sendPacketString(int command, char *str) // for a string
00399 {
                  sprintf(_sendBuffer, "%c%c%s%c", XPLDIRECT_PACKETHEADER, command, str, XPLDIRECT_PACKETTRAILER);
00400
00401
                   _transmitPacket();
00402 }
00403
00404 void XPLDirect::_transmitPacket(void)
00405 {
00406
                   streamPtr->write( sendBuffer);
00407
                   if (strlen( sendBuffer) == 64)
00408
00409
                        {\tt streamPtr->print("");}~//~{\tt apparantly}~{\tt a}~{\tt bug}~{\tt on}~{\tt some}~{\tt boards}~{\tt when}~{\tt we}~{\tt transmit}~{\tt exactly}~{\tt 64}~{\tt bytes}
00410
00411 }
00412
00413 int XPLDirect:: getHandleFromFrame() // Assuming receive buffer is holding a good frame
00414 {
00415
00416
                   int handleRet;
00417
                  holdChar = _receiveBuffer[5];
                     receiveBuffer[5] = 0;
00418
                   handleRet = atoi((char *)& receiveBuffer[2]);
00419
                   _receiveBuffer[5] = holdChar;
00420
00421
                   return handleRet;
00422 }
00423
00424 \text{ int XPLDirect::\_getPayloadFromFrame(long int } \star \text{value) } \text{// Assuming receive buffer is holding a good } \text{--} \text{--}} \text{--} \text{--}
               frame
```

```
00425 {
00426
        char holdChar;
00427
       holdChar = _receiveBuffer[15];
       \_receiveBuffer[15] = 0;
00428
00429
       *value = atol((char *)& receiveBuffer[5]);
       _receiveBuffer[15] = holdChar;
00430
00431
       return 0;
00432 }
00433
00434 int XPLDirect::_getPayloadFromFrame(float *value) // Assuming receive buffer is holding a good frame
00435 {
00436
       char holdChar:
00437
       holdChar = _receiveBuffer[15];
       _receiveBuffer[15] = 0;
00438
00439
        *value = atof((char *)&_receiveBuffer[5]);
00440
       _receiveBuffer[15] = holdChar;
00441
        return 0:
00442 }
00443
00444 int XPLDirect::_getPayloadFromFrame(char *value) // Assuming receive buffer is holding a good frame
00445 {
00446
       \verb|memcpy(value, (char *)&\_receiveBuffer[5], \_receiveBufferBytesReceived - 6);|\\
00447
       value[_receiveBufferBytesReceived - 6] = 0; // erase the packet trailer
00448
       for (int i = 0; i < _receiveBufferBytesReceived - 6; i++)</pre>
00449
00450
          if (value[i] == 7)
00451
         {
           value[i] = XPLDIRECT_PACKETTRAILER; // How I deal with the possibility of the packet trailer
00452
     being within a string
00453
00454
00455
       return 0;
00456 }
00457
00458 int XPLDirect::allDataRefsRegistered()
00459 {
00460
       return _allDataRefsRegistered;
00462
00463 int XPLDirect::registerDataRef(XPString_t *datarefName, int rwmode, unsigned int rate, float divider,
      long int *value)
00464 {
00465
        if ( dataRefsCount >= XPLDIRECT MAXDATAREFS ARDUINO)
00466
       {
00467
         return -1; // Error
00468
00469
       _dataRefs[_dataRefsCount] = new _dataRefStructure;
       _dataRefs[_dataRefsCount]->dataRefName = datarefName; // added for F() macro
00470
       _dataRefs[_dataRefsCount]->dataRefRWType = rwmode;
00471
       _dataRefs[_dataRefsCount]->divider = divider;
00472
00473
       _dataRefs[_dataRefsCount]->updateRate = rate;
00474
       _dataRefs[_dataRefsCount]->dataRefVARType = XPL_DATATYPE_INT;
00475
       _dataRefs[_dataRefsCount]->latestValue = (void *)value;
       00476
00477
00478
00479
       _dataRefsCount++;
00480
       _allDataRefsRegistered = 0;
00481
       return (_dataRefsCount - 1);
00482 }
00483
00484 int XPLDirect::registerDataRef(XPString t *datarefName, int rwmode, unsigned int rate, float divider,
      long int *value, int index)
00485 {
00486
        if (_dataRefsCount >= XPLDIRECT_MAXDATAREFS_ARDUINO)
00487
00488
         return -1;
00489
00490
       _dataRefs[_dataRefsCount] = new _dataRefStructure;
00491
       _dataRefs[_dataRefsCount]->dataRefName = datarefName;
00492
       _dataRefs[_dataRefsCount]->dataRefRWType = rwmode;
00493
       _dataRefs[_dataRefsCount]->updateRate = rate;
00494
       _dataRefs[_dataRefsCount]->divider = divider;
        _dataRefs[_dataRefsCount]->dataRefVARType = XPL_DATATYPE_INT; // arrays are dealt with on the XPlane
00495
     plugin side
       _dataRefs[_dataRefsCount]->latestValue = (void *)value;
00496
00497
       _dataRefs[_dataRefsCount]->lastSentIntValue = 0;
00498
       _dataRefs[_dataRefsCount]->arrayIndex = index; // not used unless we are referencing an array
       _dataRefs[_dataRefsCount]->dataRefHandle = -1; // invalid until assigned by xplane
00499
       _dataRefsCount++;
00500
00501
       _allDataRefsRegistered = 0;
00502
       return (_dataRefsCount - 1);
00503 }
00504
00505 int XPLDirect::registerDataRef(XPString_t *datarefName, int rwmode, unsigned int rate, float divider,
     float *value)
00506 {
```

```
if (_dataRefsCount >= XPLDIRECT_MAXDATAREFS_ARDUINO)
00508
00509
         return -1;
00510
       }
       _dataRefs[_dataRefsCount] = new _dataRefStructure;
00511
       _dataRefs[_dataRefsCount]->dataRefName = datarefName;
00512
       _dataRefs[_dataRefsCount]->dataRefRWType = rwmode;
00513
00514
       _dataRefs[_dataRefsCount]->dataRefVARType = XPL_DATATYPE_FLOAT;
00515
       _dataRefs[_dataRefsCount]->latestValue = (void *)value;
00516
       _dataRefs[_dataRefsCount]->lastSentFloatValue = -1; // force update on first loop
       _dataRefs[_dataRefsCount]->updateRate = rate;
00517
       _dataRefs[_dataRefsCount]->divider = divider;
00518
       _dataRefs[_dataRefsCount]->arrayIndex = 0;
00519
                                                    // not used unless we are referencing an array
       _dataRefs[_dataRefsCount]->dataRefHandle = -1; // invalid until assigned by xplane
00520
00521
       _dataRefsCount++;
00522
       _allDataRefsRegistered = 0;
       return (_dataRefsCount - 1);
00523
00524 }
00526 int XPLDirect::registerDataRef(XPString_t *datarefName, int rwmode, unsigned int rate, float divider,
     float *value, int index)
00527 {
00528
       if (_dataRefsCount >= XPLDIRECT_MAXDATAREFS_ARDUINO)
00529
       {
00530
         return -1;
00531
00532
       _dataRefs[_dataRefsCount] = new _dataRefStructure;
00533
       _dataRefs[_dataRefsCount]->dataRefName = datarefName;
       _dataRefs[_dataRefsCount]->dataRefRWType = rwmode;
00534
       _dataRefs[_dataRefsCount]->dataRefVARType = XPL_DATATYPE_FLOAT; // arrays are dealt with on the
00535
     Xplane plugin side
00536
       _dataRefs[_dataRefsCount]->latestValue = (void *)value;
00537
       _dataRefs[_dataRefsCount]->lastSentFloatValue = 0;
       00538
00539
       _dataRefs[_dataRefsCount]->dataRefHandle = -1; // invalid until assigned by xplane
00540
       _dataRefsCount++;
00541
00542
       _allDataRefsRegistered = 0;
00543
       return (_dataRefsCount - 1);
00544 }
00545
00546 int XPLDirect::registerDataRef(XPString_t *datarefName, int rwmode, unsigned int rate, char *value)
00547 {
00548
       if (_dataRefsCount >= XPLDIRECT_MAXDATAREFS_ARDUINO)
00549
       {
00550
         return -1;
00551
00552
       _dataRefs[_dataRefsCount] = new _dataRefStructure;
       _dataRefs[_dataRefsCount]->dataRefName = datarefName;
00553
       _dataRefs[_dataRefsCount]->dataRefRWType = rwmode;
00554
       _dataRefs[_dataRefsCount]->updateRate = rate;
00556
       _dataRefs[_dataRefsCount]->dataRefVARType = XPL_DATATYPE_STRING;
00557
       _dataRefs[_dataRefsCount]->latestValue = (void *)value;
       00558
00559
00560
       _dataRefsCount++;
00562
       _allDataRefsRegistered = 0;
00563
       return (_dataRefsCount - 1);
00564 }
00565
00566 int XPLDirect::registerCommand(XPString t *commandName) // user will trigger commands with
     commandTrigger
00567 {
00568
       if (_commandsCount >= XPLDIRECT_MAXCOMMANDS_ARDUINO)
00569
00570
         return -1;
00571
       }
       _commands[_commandsCount] = new _commandStructure;
00572
       _commands[_commandsCount]->commandName = commandName;
00574
       _commands[_commandsCount]->commandHandle = -1; // invalid until assigned by xplane
       _commandsCount++;
00575
00576
        _allDataRefsRegistered = 0; // share this flag with the datarefs, true when everything is registered
    with xplane.
00577
       return (_commandsCount - 1);
00578 }
00579
00580 // The central instance for the application
00581 XPLDirect XP(&Serial);
```

## Index

ID I	.e
_cmdPush	commandEnd
Button, 15	XPLDirect, 43
_delay	commandStart
RepeatButton, 30	XPLDirect, 44
_mux	commandTrigger
Button, 15	XPLDirect, 44
_pin	connectionStatus
Button, 15	XPLDirect, 44
_state	count
Button, 15	Timer, 41
timer	
RepeatButton, 30	datarefsUpdated
transition	XPLDirect, 44
Button, 15	DigitalIn.cpp, 60
Batton, 10	DigitalIn.h, 52
addMux	DigitalIn_, 16
DigitalIn_, 16	addMux, 16
allDataRefsRegistered	DigitalIn_, 16
XPLDirect, 43	getBit, 17
Analogin, 7	handle, 17
Analogin, 7 Analogin, 7, 8	setMux, 17
•	
calibrate, 8	down
handle, 8	Encoder, 20
raw, 8	alanaad
value, 9	elapsed
AnalogIn.cpp, 58	Timer, 41
AnalogIn.h, 50	Encoder, 18
	down, 20
begin	Encoder, 19
XPLDirect, 43	engaged, 20
Button, 9	getCommand, 20
_cmdPush, 15	handle, 21
_mux, 15	handleXP, 21
_pin, 15	pos, 21
_state, 15	pressed, 21
_transition, 15	processCommand, 21
Button, 11	released, 22
engaged, 12	setCommand, 22, 23
getCommand, 12	up, 23
handle, 12	Encoder.cpp, 61
handleXP, 13	Encoder.h, 53
pressed, 13	engaged
processCommand, 13	Button, 12
released, 14	Encoder, 20
setCommand, 14	Encoder, 20
Button.cpp, 59	getBit
• •	DigitalIn_, 17
Button.h, 51	getCommand
calibrate	Button, 12
Analogin, 8	Encoder, 20
ATRICULII. U	[ [ [ [ [ [ [ [ [ [ [ [ [ [ [ [ [ [ [

76 INDEX

Switch, 32	XPLDirect, 45, 46
Switch2, 36	released
getTime	Button, 14
Timer, 41	Encoder, 22
la consulta	RepeatButton, 26
handle	_delay, <mark>30</mark>
Analogin, 8	_timer, 30
Button, 12	handle, 29
DigitalIn_, 17	handleXP, 29
Encoder, 21	RepeatButton, 28
LedShift, 25	
RepeatButton, 29	sendDebugMessage
Switch, 32	XPLDirect, 46
Switch2, 36	sendResetRequest
handleXP	XPLDirect, 46
Button, 13	sendSpeakMessage
Encoder, 21	XPLDirect, 47
RepeatButton, 29	set
Switch, 32	LedShift, 25
Switch2, 37	set all
hasUpdated	LedShift, 25
XPLDirect, 45	setAll
,	LedShift, 26
LedShift, 24	setCommand
handle, 25	Button, 14
LedShift, 24	Encoder, 22, 23
set, 25	Switch, 33, 34
set_all, 25	Switch2, 38, 39
setAll, 26	setCycle
LedShift.cpp, 63	Timer, 42
LedShift.h, 53	setMux
,	DigitalIn_, 17
main.cpp, 49, 50	
	Switch, 30
off	getCommand, 32
Switch, 33	handle, 32
Switch2, 37	handleXP, 32
on	off, 33
Switch, 33	on, 33
on1	processCommand, 33
Switch2, 37	setCommand, 33, 34
on2	Switch, 31, 32
Switch2, 37	value, 34
	Switch.cpp, 64
pos	Switch.h, 54
Encoder, 21	Switch2, 35
pressed	getCommand, 36
Button, 13	handle, 36
Encoder, 21	handleXP, 37
processCommand	off, 37
Button, 13	on1, <mark>37</mark>
Encoder, 21	on2, <mark>37</mark>
Switch, 33	processCommand, 38
Switch2, 38	setCommand, 38, 39
	Switch2, 35, 36
raw	value, 39
AnalogIn, 8	
registerCommand	Timer, 40
XPLDirect, 45	count, 41
registerDataRef	elapsed, 41

INDEX 77

```
getTime, 41
    setCycle, 42
    Timer, 41
Timer.cpp, 67
Timer.h, 55
up
    Encoder, 23
value
    AnalogIn, 9
    Switch, 34
    Switch2, 39
xloop
    XPLDirect, 47
XPLDevices.h, 56
XPLDirect, 42
    allDataRefsRegistered, 43
    begin, 43
    commandEnd, 43
    commandStart, 44
    commandTrigger, 44
    connectionStatus, 44
    datarefsUpdated, 44
    hasUpdated, 45
    registerCommand, 45
    registerDataRef, 45, 46
    sendDebugMessage, 46
    sendResetRequest, 46
    sendSpeakMessage, 47
    xloop, 47
    XPLDirect, 43
XPLDirect.cpp, 67
XPLDirect.h, 56
```